


# Assembly Cookbook for the Apple II/IIe

part two

Don Lancaster



**Assembly Cookbook  
for the Apple™ II/IIe  
( part two )**

**by  
Don Lancaster**

**SYNERGETICS SP PRESS**  
3860 West First Street, Thatcher, AZ 85552 USA  
(928) 428-4073 <http://www.tinaja.com>

**ISBN: 978-1-882193-17-2**

Copyright c 1984, 2011 by Don Lancaster and Synergetics Press  
Thatcher, Arizona 95552

THIRD EDITION  
FIRST PRINTING 2011

All rights reserved. Reproduction or use, without express permission of editorial or pictorial content, in any manner, is prohibited. No patent liability is assumed with respect to the use of the information contained herein. While every precaution has been taken in the preparation of this book, the publisher assumes no responsibility for errors or omissions. Neither is any liability assumed for damages resulting from the use of the information contained herein.

International Standard Book Number: 978-1-882193-17-2

## part II

### The Ripoff Modules

HOW TO USE THE RIPOFF MODULES . . . . . 205

#### 0

THE EMPTY SHELL . . . . . 211

A framework you can use to create most any machine language program of your choosing.

#### 1

FILE BASED PRINTER . . . . . 229

The standard way to output short and fixed text messages using a common message file.

#### 2

IMBEDDED STRING PRINTER . . . . . 251

A much better way to "mix and match" fixed test messages that are imbedded directly into your source code.

#### 3

MONITOR TIME DELAY . . . . . 267

How to use the Apple's WAIT subroutine for animation and other system timing needs.

	<b>4</b>	
OBNOXIOUS SOUNDS .....		287
A multiple sound-effects generator that "calculates" lots of different sounds with minimum code.		

	<b>5</b>	
MUSICAL SONGS .....		301
The standard "red book tones" method of making music, along with a few improvements and upgrades.		

	<b>6</b>	
OPTION PICKER .....		321
How to do menu options or pick modules using the forced subroutine return method.		

	<b>7</b>	
RANDOM NUMBER .....		345
A fast and usable way to generate "random" numbers, without the fatal flaws of the Applesloth "RND" code.		

	<b>8</b>	
SHUFFLE .....		363
An extremely fast "random exchange" method of rearranging an array of numbers or file values.		

## Appendixes

	<b>A</b>	
DIFFERENCES BETWEEN "OLD" AND "NEW" EDASM .....		381

	<b>B</b>	
SOME NAMES AND NUMBERS .....		387

	<b>C</b>	
LABEL LISTS TO COPY .....		393

INDEX .....		399
-------------	--	-----

COMPANION DISKETTE AND VOICE HOTLINE .....		407
--	--	-----

**part two**  
**The Ripoff Modules**

**by**  
**Don Lancaster**

**SYNERGETICS SP PRESS**  
3860 West First Street, Thatcher, AZ 85552 USA  
(928) 428-4073 <http://www.tinaja.com>

**ISBN: 978-1-882193-17-2**

## HOW TO USE THE RIPOFF MODULES

The *Ripoff Modules* are a series of nine interactive demos designed to show you how to handle many common Apple machine language programming problems. Each module is listable, completely documented, and out in the open where you can easily access it.

I've tried to emphasize what really gets used, since just about all programming books and most program libraries center on largely outdated, cumbersome, and irrelevant dino stuff, rather than answering the real gut questions, such as "What's the best way to handle lots of text messages that might be mixed and matched together?" "Can I do a fast and well-behaved random number generator?" "Show me how to handle sound effects and musical songs;" or "How can I quickly shuffle cards or rearrange array values?"

Originally, I wanted to have lots of short demo modules. But, there are so many different important things to learn in Apple assembly language that there is simply no way to cram everything into a single book. So, instead, I decided to take the nine things that beginning assembly students seem to have the most trouble with, and expand on these in some depth.

All nine modules and bunches of other goodies are also available on a sanely priced and crammed-full companion diskette, which you can order using the card in the back of this book.

Naturally, full source code is included for each and every module. Of course, the diskette is totally unlocked, unprotected, and fully copyable. You have your choice of EDASM or S-C Assembler formats.

Most other assemblers will accept either of these formats, or else will provide a way to convert them.

A companion voice hotline service goes with this support diskette, similar to the hotline that is provided to *Enhancing* users. This support service is free, except for the usual phone charges.

You are, of course, totally free to adapt and use these ripoff modules in any way you want for any purpose. Just play fair. Give credit for any commercial use and don't try to compete head on.

Most ordinary Apple modules and subroutines are *result* oriented. This means that they are trying to get some job done as quickly and as compactly as possible. Our ripoff modules are *method* oriented instead. I have picked the modules to show you certain ways of handling different programming tasks. I've tried to make each method as mainstream and innovative as possible.

Which means that most of these modules will not have you gripping the edge of your chair in suspense, or rolling in the aisles with laughter over what they are actually doing. The modules are not intended to be arcade-quality entertainment, nor are they supposed to give you spectacular results, when used one at a time by themselves. The modules are intended instead to be a learning tool that shows you how to tackle the real gut issues involved in creating your own Apple machine language programs.

There are lots of ways you can use the ripoff modules . . .

USING THE RIPOFF MODULES
Read about them
Run them
List them
Tear them apart
Study them
Change them
Adapt them
Close the loop

Here's how to claim these modules as your own, and to add them to your own programs: First read the background text that goes with each module, so you can see what the module is intended to do. It turns out that any particular programming technique works well for some *range* of complexity, and may be overkill for simpler things and cumbersome or inefficient for very elaborate jobs. So, be sure you understand the intended use of each module, along with any simpler or more complex alternatives.

Next, run the program and watch or listen to it doing its thing. Since many of the modules will stand on their own, what they do will be pretty much limited to pointing out how they work and how they handle a certain task. In some cases, I've "trumped up" a simple example of something complex that the module is supposed to handle. Now, there may be a better way to get the *result* shown by the simple example, but, once again, that's not our point or purpose. We're after *method* here.



Then, reset to the monitor and list the program. Use the “tearing method” from Enhancement 3 of *Enhancing Your Apple II*, Volume I (Sams 21822). Color code each and every disassembled line with a page highlighter, following the *tearing* guidelines. Do this *before* you study the actual source code in depth. The reason is to gain practice reading and understanding machine language listings, particularly for those modules or programs for which you do *not* have source code.

The next step is to compare your “torn” listing against the actual source code shown here in these modules, to be sure you understand exactly what is happening when.

So much for the *analysis*. When you understand the point and purpose of each module, try some *synthesis*.

Capture a copy of the source code for the module, using an assembler of your choice. Then, make some fairly simple changes in the source code, so it will do something “alike but different somehow.” Save this to a new diskette, and then assemble and run your new object code. After that, add some bells and whistles to the module’s demo so it becomes longer, more interesting, or more exciting.

Now the fun begins. Rewrite the module source code one more time. Only now, make it do something you want it to do in the way you want it done, rather than the way that is shown here. Test your object code, and then actually use it in a larger program of your choosing.

Needless to say, the more time and effort you spend in understanding and capturing these modules, the more value they will be to you.

Finally, close the loop. Use the response card in back or call the hotline to let me know how you have used the existing modules and which new ones you need or would like to see.

Some of the later modules will “borrow” portions of earlier ones to keep the code simple and not reinvent the wheel. We have tried to note what is needed where. The companion diskette also includes an object code program called THE WHOLE BALL OF WAX, which combines all of the ripoff modules together all at once, along with a unifying demo.

Here’s a summary of the ripoff modules and what they are intended to do . . .

## **RIPOFF MODULE SUMMARY**

### **0. THE EMPTY SHELL—**

A framework you can use to create most any machine language program of your choosing.

### **1. FILE BASED PRINTER—**

The standard way to output short and fixed text messages using a common message file.

### **2. IMBEDDED STRING PRINTER—**

A much better way to “mix and match” fixed text messages that are imbedded directly into your source code.

### **3. MONITOR TIME DELAY—**

How to use the Apple’s WAIT subroutine for animation and other system timing needs.

### **4. OBNOXIOUS SOUNDS—**

A multiple sound effects generator that “calculates” lots of different sounds with minimum code.

**5. MUSICAL SONGS—**

The standard “red book tones” method of making music, along with a few improvements and upgrades.

**6. OPTION PICKER—**

How to do menu options or pick modules using the forced subroutine return method.

**7. RANDOM NUMBERS—**

A fast and usable way to generate “random” numbers without the fatal flaws of the Applesloth “RND” code.

**8. SHUFFLE—**

An extremely fast “random exchange” method of rearranging an array of numbers or file values.

The ripoff modules each take up one to three pages of memory. Together they sit from hex \$6000 through \$7300. The location of each module is shown in its source code.

If you want to interact between Applesloth and these modules, just do a HIMEM: 24575 as your first program line. This will protect the module space from being plowed. You can access the code on a PEEK and POKE basis, using your copy of *The Hexadecimal Chronicles* (Sams 21802) to show you the linking points.

One thing we have not, and will not do, is show you BASIC equivalents for the ripoff modules. The whole point of learning assembly language programming is to do so in ways that optimize the use of machine language. Thus, you *never* do something the way BASIC does. That’s not even wrong. Only dumb.

On to the modules . . .

## THE EMPTY SHELL

**a framework you can use to  
create most any machine lan-  
guage program**

Here are 500 lines of source code that do—absolutely nothing! It's called the *empty shell* and you use it as a framework for building your own source codes.

Actually, you'll find the empty shell doing lots of good things for you. Since it is usually much easier to edit *existing* code than to *enter* new code on most assemblers, the empty shell makes writing your custom source codes much faster. Secondly, the empty shell forces you to put decent documentation into the program ahead of time, rather than waiting until the last minute and then not doing it. This also keeps your style consistent from program to program.

The empty shell should also give you code that is far cleaner and more understandable. Finally, and most conveniently, the empty shell contains a long machine readable list of practically all of the useful Apple II and IIe subroutines and entry points. Rather than looking these up in a dozen different places, you simply *eliminate* the ones you do *not* want.

The empty shell is, of course, structure, and as we've seen, structure of any sort in a computer program is inherently despicable and evil. Nonetheless, we will use the sixteen part structure we looked at back in chapter four.

All the rest of the ripoff modules will show us examples of how the empty shell works and how to use it.

But, where do you start? . . .

**To use the EMPTY SHELL.SOURCE, first eliminate what you do *not* want or need. This is best done *backward* from end to beginning.**

**Then, edit or change what is left to create your new source code. This is usually done *forward* from start to finish.**

First, of course, you will want to customize and personalize your own EMPTY SHELL.SOURCE by putting your own name, company, and copyright notice where mine now are. Do not rewrite to the companion diskette. Instead, save everything new on your own new diskettes. That way, you can always return to the originals if disaster strikes.

Here's some more detail on how to go about . . .

#### USING THE EMPTY SHELL

1. Assemble EMPTY SHELL.SOURCE and make an assembly listing hard copy. Then reload EMPTY SHELL.SOURCE into your assembler or "new way" word processor.
2. Start at the end of the source code and eliminate what you do *not* want. First, check the last line and decide whether you want to use LST OFF or LST ON. LST ON is a good choice for early program versions.
3. Decide how long your program files are to be. If you are using no DFB style files, or if you need less than 256 bytes of single-byte file values, then shorten the DFB section by deleting lines. If you need more file bytes, extend by copying.
4. Go to your hard copy and check off the hooks and constants you are going to use. If you are "old way" editing, put these in alphabetical order and then copy them to the end of their source code listings. Then delete all the unused hooks and constants.
5. Begin editing from the first line. Change the origin, then the title box. Continue editing by rewriting the "What it does," "How to use it," "Gotchas," "Enhancements," and "Random Comments." Don't worry too much about getting these perfect, since you will almost certainly change them as you edit and debug your source code.
6. Add any new hooks and constants that you want to predefine.
7. Enter your high level code and the documentation for the big lumps. Overwrite the NOPs with actual code and comments. Should you need more room, go to the assembler's insert mode and continue.
8. Do the same thing for the little lumps and the crumbs. Then enter your file values.
9. Assemble your new source code and do an assembler listing. Then repair all errors and repeat the process until you get an "error-free" result.
10. Eliminate any spurious lines and comments that may be left over from the original and reassemble.
11. Test your code, and proceed debugging from here just as you would with any other source code.

I've tried to include a fairly complete list of hooks. But note that not every hook will work on every version of Apple. For instance, STEP and TRACE will only run with an old autostart ROM, while VBL and ALTCSN will only perform on an Apple IIe.

By the way, I've shortened some of the IIe labels so they are only seven or fewer characters long. You may prefer to use the "official" labels instead.

If you use any "version-specific" Apple features, be sure to include tests in your program to make sure you have the right machine in use. In general, most "mainstream" autostart programs will run on a IIe, but programs that make use of new IIe features will not work on older versions, and may even hang. If you must use some of the "oldies but goodies," it may be best to drag along the needed code *inside* your own program. Stock ID routines are included with "new" EDASM.

Should you be "new way" editing your empty shell, just delete anything unwanted or unneeded as it comes up. Once again, it is best to work from bottom to top in reverse order.

The easiest "old way" means of getting rid of extra and unwanted hooks is to copy those you need to the end of the hook listing and then delete all of the original hooks in one swell foop. With "new way" editing, just chop out what you don't need on the way by.

Since EMPTY SHELL.SOURCE is so complete, it ends up a tad long and rather slow in loading. After you have worked with it for a while, you might like to do a "short form" version of EMPTY SHELL.SOURCE that more meets your specific programming needs. If you do this, keep a printed copy of the original on hand for reference.

A tip . . .

**ALWAYS do some minor fixup and pretty printing at the same time you make any important source code corrections.**

Whenever you are fixing up fatal errors and making heavy changes in your source code, spend some time to clean up your documentation, improve page breaks, insert spacing, do pretty printing, eliminate unwanted lines, and cosmetic stuff like this. Each reassembly should include both heavy and light repairs.

A good goal is one line of cosmetic fix for each line of heavy fix.

This way, by the time you finally get your program debugged and working, it also will be pretty much properly documented and attractive to look at. Whatever you do, don't save the documentation for last. Start with your documentation. Sharpen, improve, clarify as you go along.

All the rest of the ripoff modules were written using the EMPTY SHELL.SOURCE. Use these as study examples, and then work up your own custom shell that meets your personal programming needs.

### MIND BENDERS

- Write a WPL program that automates your empty shell setup, through use of prompts and directed questions.
- If your “new way” word processor has glossary or user-defined keys, show how to use these for single key macros and other speedup tricks.
- Solve the new way tabbing problem so that active source code lines position themselves correctly, yet comment lines remain intact.
- What tests should your source code include to make sure of . . .
  - uppercase vs lowercase?
  - ll vs lle?
  - 40 vs 80 column?
  - paddles vs joystick?
  - joystick orientation?



PROGRAM RM-0  
THE EMPTY SHELL

----- NEXT OBJECT FILE NAME IS EMPTY SHELL

6000:           3           ORG \$6000           ; ORIGIN GOES HERE

```
6000:           5 ; *****
6000:           6 ; *
6000:           7 ; *           -< THE EMPTY SHELL >-       *
6000:           8 ; *
6000:           9 ; *           (DUMMY PROGRAM)           *
6000:          10 ; *
6000:          11 ; *           VERSION 1.0 ($6000-$6160)       *
6000:          12 ; *
6000:          13 ; *           5-24-83                       *
6000:          14 ; *.....*
6000:          15 ; *
6000:          16 ; *           COPYRIGHT C 1983 BY           *
6000:          17 ; *
6000:          18 ; *           DON LANCASTER AND SYNERGETICS   *
6000:          19 ; *           BOX 1300, THATCHER AZ., 85552   *
6000:          20 ; *
6000:          21 ; *           ALL COMMERCIAL RIGHTS RESERVED   *
6000:          22 ; *
6000:          23 ; *****
```

6000:           25 ;           \*\*\* WHAT IT DOES \*\*\*

```
6000:           27 ;       THIS PROGRAM IS A DUMMY SHELL USED AS A STARTING
6000:           28 ;       POINT FOR YOUR OWN ASSEMBLY LANGUAGE PROGRAMS.
6000:           29 ;
6000:           30 ;
6000:           31 ;
6000:           32 ;
```

6000:           34 ;           \*\*\* HOW TO USE IT \*\*\*

```
6000:           36 ;       TO USE, EDIT THE PROGRAM BY MOVING THE ORIGIN,
6000:           37 ;       CHANGING THE TITLE, REMOVING EXTRA EQU'S, ADDING
6000:           38 ;       YOUR OWN WORKING CODE, ALTERING THE DATA FILES
6000:           39 ;       AND DOING WHATEVER ELSE MAY BE NEEDED TO BUILD
6000:           40 ;       YOUR OWN CUSTOM ASSEMBLED PROGRAM OR MODULE.
6000:           41 ;
```

## PROGRAM RM-0, CONT'D . . .

```
6000:      44 ;          *** GOTCHAS ***
6000:      46 ;  ANYTHING ESSENTIAL FOR USE OR UNDERSTANDING OF THE
6000:      47 ;  PROGRAM GETS PUT HERE.  THIS INCLUDES SPECIAL NEEDS
6000:      48 ;  SUCH AS EXTRA MEMORY, ANY COMPANION CODE MODULES, OR
6000:      49 ;  ANY SPECIAL HARDWARE.
6000:      50 ;
6000:      51 ;

6000:      53 ;          *** ENHANCEMENTS ***
6000:      55 ;  PUT ANY ADD-ONS, "EXTRA TRICKS", OR SPECIAL
6000:      56 ;  USES HERE.  INCLUDE USE TIPS AND APPLICATIONS.
6000:      57 ;
6000:      58 ;
6000:      59 ;
6000:      60 ;

6000:      62 ;          *** RANDOM COMMENTS ***
6000:      64 ;  IF THERE IS SOMETHING ELSE YOU WANT TO SAY THAT'S
6000:      65 ;  NOT ALL THAT IMPORTANT, YOU CAN ADD IT IN THIS SPACE.
6000:      66 ;
6000:      67 ;
6000:      68 ;
6000:      69 ;
```

## PROGRAM RM-0, CONT'D . . .

```

6000:          72 ;          *** HOOKS ***

0020:          74 WNDLFT EQU $20      ; SCROLL WINDOW LEFT
0021:          75 WNDWDTH EQU $21     ; SCROLL WINDOW WIDTH
0022:          76 WNDTOP EQU $22      ; SCROLL WINDOW TOP
0023:          77 WNDBOT EQU $23      ; SCROLL WINDOW BOTTOM
0024:          78 CH EQU $24          ; CURSOR HORIZONTAL
0025:          79 CV EQU $25          ; CURSOR VERTICAL
0026:          80 GBASL EQU $26       ; LORES BASE LOW
0027:          81 GBASH EQU $27       ; LORES BASE HIGH
0028:          82 BASL EQU $28        ; TEXT BASE LOW
0029:          83 BASH EQU $29        ; TEXT BASE HIGH
002C:          84 HEND EQU $2C        ; LORES RIGHT END H LINE
002D:          85 VBOT EQU $2D        ; LORES BOTTOM OF V LINE
0030:          86 COLOR EQU $30       ; LORES COLOR
0031:          87 INVFLG EQU $31      ; NORMAL/INVERSE/FLASH (FF,7F,3F)
0033:          88 PROMPT EQU $33      ; HOLDS PROMPT SYMBOL
0036:          89 CSWL EQU $36        ; OUTPUT CHARACTER HOOK LOW
0037:          90 CSWH EQU $37        ; OUTPUT CHARACTER HOOK HIGH
0038:          91 KSWL EQU $38        ; INPUT CHARACTER HOOK LOW
0039:          92 KSWH EQU $39        ; INPUT CHARACTER HOOK HIGH
004E:          93 RNDL EQU $4E        ; RANDOM NUMBER LOW
004F:          94 RNDH EQU $4F        ; RANDOM NUMBER HIGH

0100:          96 STACK EQU $0100     ; STACK PAGE ACCESS

0200:          98 KEYBUF EQU $0200    ; KEYBUFFER START

03D0:          100 DOSWRM EQU $03D0   ; DOS WARM START JMP
03D3:          101 DOSCLD EQU $03D3   ; DOS COLD START JMP
03D6:          102 DOSFLM EQU $03D6   ; DOS FILE MANAGER JUMP
03D9:          103 DOSRWTS EQU $03D9  ; DOS RWTS JUMP
03DC:          104 DOSIPRM EQU $03DC  ; DOS FILE PARAMETER FIND JUMP
03E3:          105 DOSRWLS EQU $03E3  ; DOS RWTS PARAMETER FIND JUMP
03EA:          106 DOSHOOK EQU $03EA  ; DOS HOOK RECONNECT JUMP
03F0:          107 BRK EQU $03F0      ; BREAK ADDRESS (AUTOSTART& 2E ONLY!)
03F2:          108 SOFTEV EQU $03F2   ; SOFT RESET (AUTOSTART & 2E ONLY!)
03F4:          109 PWRDUP EQU $03F4   ; WARM START EOR CHECKSUM
03F5:          110 AMPERV EQU $03F5   ; APPLESOFT "&" JUMP
03F8:          111 USRADR EQU $03F8   ; CTRL-Y JUMP
03FB:          112 NMI EQU $03FB     ; NON-MASKABLE INTERRUPT JUMP
03FE:          113 IRQLOC EQU $03FE  ; INTERRUPT ADDRESS LOW

0400:          115 TEXTP1 EQU $0400   ; START OF TEXT PAGE ONE
0800:          116 TEXTP2 EQU $0800   ; START OF TEXT PAGE TWO
2000:          117 HIRES P1 EQU $2000 ; START OF HIRES PAGE ONE
4000:          118 HIRES P2 EQU $4000 ; START OF HIRES PAGE TWO

```

## PROGRAM RM-0, CONT'D . . .

```

C000:      121 IOADR   EQU   $C000   ; KEYBOARD INPUT
C010:      122 KBDSTR EQU   $C010   ; KEYSTROBE RESET
C020:      123 TAPEOUT EQU   $C020   ; CASSETTE OR AUDIO OUT
C030:      124 SPKR   EQU   $C030   ; SPEAKER CLICK OUTPUT
C040:      125 STROBE EQU   $C040   ; GAME CONNECTOR STROBE
C050:      126 TXTCLR EQU   $C050   ; GRAPHICS ON SOFT SWITCH
C051:      127 TXTSET EQU   $C051   ; TEXT ON SOFT SWITCH
C052:      128 MIXCLR EQU   $C052   ; FULL SCREEN SOFT SWITCH
C053:      129 MIXSET EQU   $C053   ; MIXED SCREEN SOFT SWITCH
C054:      130 LOWSCR EQU   $C054   ; PAGE ONE SOFT SWITCH
C055:      131 HISCR  EQU   $C055   ; PAGE TWO SOFT SWITCH
C056:      132 LORES  EQU   $C056   ; LORES SOFT SWITCH
C057:      133 HIRES  EQU   $C057   ; HIRES SOFT SWITCH
C060:      134 PB4    EQU   $C060   ; CASS IN + "FOURTH" PB INPUT "SW3"
C061:      135 PB1    EQU   $C061   ; OPEN APPLE + "FIRST" PB INPUT "SW0"
C062:      136 PB2    EQU   $C062   ; CLOSED APPLE + "SECOND" PB INPUT "S
C063:      137 PB3    EQU   $C063   ; "THIRD" PUSHBUTTON INPUT "SW2"
C064:      138 PDL0   EQU   $C064   ; GAME PADDLE 0 ANALOG IN
C065:      139 PDL1   EQU   $C065   ; GAME PADDLE 1 ANALOG IN
C066:      140 PDL2   EQU   $C066   ; GAME PADDLE 2 ANALOG IN
C067:      141 PDL3   EQU   $C067   ; GAME PADDLE 3 ANALOG IN
C070:      142 PTRIG  EQU   $C070   ; ANALOG PADDLE RESET

C080:      144 STEP00 EQU   $C080   ; DISK STEPPER PHASE 0 OFF
C081:      145 STEP01 EQU   $C081   ; DISK STEPPER PHASE 0 ON
C082:      146 STEP10 EQU   $C082   ; DISK STEPPER PHASE 1 OFF
C083:      147 STEP11 EQU   $C083   ; DISK STEPPER PHASE 1 ON
C084:      148 STEP20 EQU   $C084   ; DISK STEPPER PHASE 2 OFF
000C:      149 STEP21 EQU   $C085   ; DISK STEPPER PHASE 2 ON
C086:      150 STEP30 EQU   $C086   ; DISK STEPPER PHASE 3 OFF
C087:      151 STEP31 EQU   $C087   ; DISK STEPPER PHASE 3 ON
C088:      152 MOTON  EQU   $C088   ; DISK MAIN MOTOR OFF
C089:      153 MOTOFF EQU   $C089   ; DISK MAIN MOTOR ON
C08A:      154 DRVOEN EQU   $C08A   ; DISK ENABLE DRIVE 1
C08B:      155 DRVLEN EQU   $C08B   ; DISK ENABLE DRIVE 2
C08C:      156 Q6CLR  EQU   $C08C   ; DISK Q6 CLEAR
C08D:      157 Q6SET  EQU   $C08D   ; DISK Q6 SET
C08E:      158 Q7CLR  EQU   $C08E   ; DISK Q7 CLEAR
C08F:      159 Q7SET  EQU   $C08F   ; DISK Q7 SET

E000:      161 BASICLD EQU   $E000   ; ENTER BASIC COLD
E003:      162 BASICWM EQU   $E003   ; RE-ENTER BASIC WARM

F3D8:      164 HGR2    EQU   $F3D8   ; APPLESOFT CLEAR TO HIRES 2
F3E2:      165 HGR    EQU   $F3E2   ; APPLESOFT CLEAR TO HIRES 1
F3F4:      166 BKGND  EQU   $F3F4   ; APPLESOFT HIRES BACKGROUND CLEAR
F6F0:      167 HCOLOR EQU   $F6F0   ; APPLESOFT HIRES COLOR SELECT
F411:      168 HPOSN  EQU   $F411   ; APPLESOFT HIRES POSITION
F457:      169 HPLOT   EQU   $F457   ; APPLESOFT HIRES PLOT

```

## PROGRAM RM-0, CONT'D . . .

```

F800:      172 PLOT      EQU  $F800      ; PLOT LORES BLOCK
F819:      173 HLINE    EQU  $F819      ; HORIZ LORES LINE
F828:      174 VLINE    EQU  $F828      ; VERTICAL LORES LINE
F832:      175 CLRSCR   EQU  $F832      ; CLEAR FULL LORES SCREEN
F836:      176 CLRTOP   EQU  $F836      ; CLEAR TOP LORES SCREEN
F847:      177 GBSCALC  EQU  $F847      ; LORES BASE CALCULATION
F85F:      178 NEXTCOL  EQU  $F85F      ; INCREASE LORES COLOR BY 3
F864:      179 SETCOL   EQU  $F864      ; SET LORES COLOR
F871:      180 SCRN     EQU  $F871      ; READ LORES SCREEN COLOR
F941:      181 PRNTAX   EQU  $F941      ; OUTPUT A THEN X AS HEX
F948:      182 PRBLNK   EQU  $F948      ; OUTPUT 3 SPACES VIA HOOKS
F94A:      183 PRBL2    EQU  $F94A      ; OUTPUT X BLANKS VIA HOOKS

FAD7:      185 REGDSP   EQU  $FAD7      ; DISPLAY WORKING REGISTERS
FB1E:      186 PREAD    EQU  $FB1E      ; READ GAME PADDLE X
FB2F:      187 INIT     EQU  $FB2F      ; INITIALIZE TEXT SCREEN
FB93:      188 SETTXT   EQU  $FB93      ; SET UP TEXT SCREEN (NOT 2E!)
FB40:      189 SETGR    EQU  $FB40      ; SET UP GRAPHICS SCREEN
FB4B:      190 SETWND   EQU  $FB4B      ; SET NORMAL TEXT WINDOW
FBC1:      191 BASCALC  EQU  $FBC1      ; CALCULATE TEXT BASE ADDRESS (NOT 2E!)
FBD9:      192 BELL1    EQU  $FBD9      ; BEEP SPEAKER IF CTRL-G
FBE4:      193 BELL2    EQU  $FBE4      ; BEEP SPEAKER ONCE
FBF4:      194 ADVANCE  EQU  $FBF4      ; TEXT CURSOR ONE TO RIGHT
FBFD:      195 VIDOUT   EQU  $FBFD      ; OUTPUT ASCII TO SCREEN ONLY

FC10:      197 BS       EQU  $FC10      ; BACKSPACE SCREEN
FC1A:      198 UP       EQU  $FC1A      ; MOVE SCREEN CURSOR UP ONE LINE
FC22:      199 VTAB    EQU  $FC22      ; VERTICAL SCREEN TAB USING CV
FC24:      200 VTABA    EQU  $FC24      ; VERTICAL SCREEN TAB USING A
FC66:      201 ESC1     EQU  $FC66      ; PROCESS ESCAPE CURSOR MOVES
FC42:      202 CLREOP   EQU  $FC42      ; CLEAR TO END OF PAGE
FC58:      203 HOME    EQU  $FC58      ; CLEAR TEXT SCREEN AND HOME CURSOR
FC62:      204 CR       EQU  $FC62      ; CARRIAGE RETURN TO SCREEN
FC66:      205 LF       EQU  $FC66      ; LINEFEED TO SCREEN ONLY
FC70:      206 SCROLL  EQU  $FC70      ; SCROLL TEXT SCREEN UP ONE
FC9C:      207 CLEOL   EQU  $FC9C      ; CLEAR TEXT TO END OF LINE
FCA8:      208 WAIT    EQU  $FCA8      ; TIME DELAY SET BY ACCUMULATOR
FD0C:      209 RDKEY   EQU  $FD0C      ; GET INPUT CHARACTER VIA HOOKS
FD1B:      210 KEYIN   EQU  $FD1B      ; READ THE APPLE KEYBOARD
FD35:      211 RDCHAR  EQU  $FD35      ; GET KEY AND PROCESS ESC A-F
FD62:      212 CANCEL  EQU  $FD62      ; CANCEL KEYBOARD LINE ENTRY
FD67:      213 GETLNZ  EQU  $FD67      ; CR THEN GET KEYBOARD INPUT LINE
FD6A:      214 GETLN   EQU  $FD6A      ; GET KEYBOARD INPUT LINE
FD6F:      215 GETLN1  EQU  $FD6F      ; GET KBD INPUT, NO PROMPT
FD8B:      216 CROUT1  EQU  $FD8B      ; CLEAR EOL THEN CR VIA HOOKS
FD8E:      217 CROUT   EQU  $FD8E      ; OUTPUT CR VIA HOOKS
FDDA:      218 PRBYTE  EQU  $FDDA      ; OUTPUT FULL A IN HEX TO HOOKS
FDE3:      219 PRHEX   EQU  $FDE3      ; OUTPUT LOW A IN HEX TO HOOKS
FDED:      220 COUT    EQU  $FDED      ; OUTPUT CHARACTER VIA HOOKS
FDF0:      221 COUT1   EQU  $FDF0      ; OUTPUT CHARACTER TO SCREEN

```

## PROGRAM RM-0, CONT'D . . .

```

FE2C:      224 MOVE      EQU  $FE2C      ; MOVE BLOCK OF MEMORY
FE36:      225 VERIFY   EQU  $FE36      ; VERIFY BLOCK OF MEMORY
FE5E:      226 LIST     EQU  $FE5E      ; DISASSEMBLE 20 INSTRUCTIONS
FE63:      227 LIST2    EQU  $FE63      ; DISASSEMBLE "A" INSTRUCTIONS
FE80:      228 SETINV   EQU  $FE80      ; PRINT INVERSE TEXT TO SCREEN
FE84:      229 SETNORM  EQU  $FE84      ; PRINT NORMAL TEXT TO SCREEN
FE93:      230 SETVID   EQU  $FE93      ; GRAB OUTPUT HOOKS FOR SCREEN
FEB0:      231 XBASIC   EQU  $FEB0      ; GO BASIC, DESTROYING OLD
FEB3:      232 BASCON   EQU  $FEB3      ; GO BASIC, CONTINUING OLD
FEC2:      233 TRACE    EQU  $FEC2      ; START TRACING (OLD ROM ONLY!)
FEC4:      234 STEP     EQU  $FEC4      ; SINGLE STEP (OLD ROM ONLY!)
FECD:      235 WRITE    EQU  $FECD      ; WRITE TO CASSETTE TAPE
FEFD:      236 READ     EQU  $FEFD      ; READ FROM CASSETTE TAPE
FF2D:      237 PRERR    EQU  $FF2D      ; PRINT "ERR" TO OUTPUT HOOK
FF3A:      238 BELL     EQU  $FF3A      ; OUTPUT BELL TO HOOKS
FF3F:      239 IORESR   EQU  $FF3F      ; RESTORE ALL WORKING REGISTERS
FF4A:      240 IOSAVE   EQU  $FF4A      ; SAVE ALL WORKING REGISTERS
FF58:      241 RETURN   EQU  $FF58      ; "GUARANTEED" RETURN
FF59:      242 OLDRST   EQU  $FF59      ; OLD RESET, NO AUTOSTART
FF65:      243 MON      EQU  $FF65      ; ENTER MONITOR AND BEEP SPEAKER
FF69:      244 MONZ     EQU  $FF69      ; ENTER MONITOR QUIETLY
FFA7:      245 GETNUM   EQU  $FFA7      ; ASCII TO HEX IN 3E & 3F

6000:      247 ;          *** HOOKS FOR 2E ONLY! ***

C000:      249 CLR80CO  EQU  $C000      ; 80 STORE OFF (WRITE ONLY)
C001:      250 SET80CO  EQU  $C001      ; 80 STORE ON (WRITE ONLY)
C002:      251 RAMRDMN  EQU  $C002      ; READ MAIN MEMORY (WRITE ONLY)
C003:      252 RAMRDAX  EQU  $C003      ; READ AUXILIARY MEMORY (WRITE ONLY)
C004:      253 RAMWRMN  EQU  $C004      ; WRITE MAIN MEMORY (WRITE ONLY)
C005:      254 RAMWRAX  EQU  $C005      ; WRITE AUXILIARY MEMORY (WRITE ONLY)
C006:      255 SLOTXRM  EQU  $C006      ; INTERNAL ROM AT CX00 (WRITE ONLY)
C007:      256 SLOTXEX  EQU  $C007      ; SLOT ROM AT CX00 (WRITE ONLY)

C008:      258 MAINZP   EQU  $C008      ; USE MAIN ZERO PAGE (WRITE ONLY)
C009:      259 ALTZP    EQU  $C009      ; USE ALTERNATE ZERO PAGE (WRITE ONLY)
C00A:      260 SLOT3RM  EQU  $C00A      ; SLOT #3 INTERNAL ROM (WRITE ONLY)
C00B:      261 SLOT3EX  EQU  $C00B      ; SLOT #3 EXTERNAL ROM (WRITE ONLY)
C00C:      262 OFF80CL  EQU  $C00C      ; TURN 80 COLUMN OFF (WRITE ONLY)
C00D:      263 ON80COL  EQU  $C00D      ; TURN 80 COLUMN ON (WRITE ONLY)
C00E:      264 ALTCSOF  EQU  $C00E      ; USE MAIN CHARACTER SET (WRITE ONLY)
C00F:      265 ALTCSOEN EQU  $C00F      ; USE ALT CHARACTER SET (WRITE ONLY)

```

## PROGRAM RM-0, CONT'D . . .

```
C013:      268 RAMRDS EQU $C013      ; READ RAMREAD SWITCH (READ ONLY)
C014:      269 RAMWTS EQU $C014      ; READ RAMWRITE SWITCH (READ ONLY)
C015:      270 SLTCXS EQU $C015      ; READ SLOT CX SWITCH (READ ONLY)
C016:      271 ALTZPS EQU $C016      ; READ ZERO PAGE SWITCH (READ ONLY)
C017:      272 SLTC3S EQU $C017      ; READ SLOT C3 SWITCH (READ ONLY)

C018:      274 S80STR EQU $C018      ; READ 80STORE SWITCH (READ ONLY)
C019:      275 VBL EQU $C019          ; VERT. BLANKING >80=BLANK (READ ONLY)
C01A:      276 TEXTS EQU $C01A       ; READ TEXT SWITCH (READ ONLY)
C01B:      277 MIXEDS EQU $C01B      ; READ MIXED GR SWITCH (READ ONLY)
C01C:      278 PAGE2S EQU $C01C      ; READ PAGE 2 SWITCH (READ ONLY)
C01D:      279 HIRESS EQU $C01D      ; READ HIRES SWITCH (READ ONLY)
C01E:      280 ALTCSS EQU $C01E      ; READ ALTCHAR SET SWITCH (READ ONLY)
C01F:      281 S80COL EQU $C01F      ; READ 80 COLUMN SWITCH (READ ONLY)

C080:      283 RB2RAM EQU $C080      ; READ BANK 2 RAM
C081:      284 WB2RAM EQU $C081      ; WRITE BANK 2 RAM, READ ROM
C082:      285 RROM EQU $C082        ; READ ROM ONLY, NO WRITE
C083:      286 RWRAM2 EQU $C083      ; READ & WRITE RAM2 (HIT TWICE!)
C088:      287 RRAM1 EQU $C088       ; READ BANK1 RAM
C089:      288 WRAM1 EQU $C089       ; WRITE BANK1 RAM, READ ROM
C08A:      289 RB1ROM EQU $C08A      ; READ BANK1 ROM
C08B:      290 RWRAM1 EQU $C08B      ; READ & WRITE RAM1 (HIT TWICE!)

6000:      292 ;                      *** CONSTANTS ***
6000:      293 ;                      *** TEXTFILE COMMANDS ***

0088:      295 B EQU $88              ; BACKSPACE
008D:      296 C EQU $8D              ; CARRIAGE RETURN
0084:      297 D EQU $84              ; DOS ATTENTION
008C:      298 F EQU $8C              ; FORMFEED
0087:      299 G EQU $87              ; RING GONG
008A:      300 L EQU $8A              ; LINEFEED
0060:      301 P EQU $60              ; FLASHING PROMPT
0000:      302 X EQU $00              ; END OF MESSAGE
```

## PROGRAM RM-0, CONT'D . . .

```
6000:      305 ;          *** BIG LUMPS ***
6000:      306 ;          *** MAIN PROGRAM ***
6000:      307 ;          *** HIGH LEVEL CODE ***

6000:      309 ;          ADD ANY COMMENTS HERE THAT ARE
6000:      310 ;          SPECIFIC TO THE BIG LUMPS.
6000:      311 ;
6000:      312 ;
6000:      313 ;
6000:      314 ;

6000:EA    316 START1  NOP          ; YOUR HIGH LEVEL CODE STARTS HERE
6001:EA    317          NOP          ; AND GOES ON AS FAR AS NEEDED.
6002:EA    318          NOP          ;
6003:EA    319          NOP          ;
6004:EA    320          NOP          ;
6005:EA    321          NOP          ;
6006:EA    322          NOP          ;
6007:EA    323          NOP          ;

6008:EA    325          NOP          ;
6009:EA    326          NOP          ;
600A:EA    327          NOP          ;
600B:EA    328          NOP          ;
600C:EA    329          NOP          ;
600D:EA    330          NOP          ;
600E:EA    331          NOP          ;
600F:EA    332          NOP          ;

6010:EA    334          NOP          ;
6011:EA    335          NOP          ;
6012:EA    336          NOP          ;
6013:EA    337          NOP          ;
6014:EA    338          NOP          ;
6015:EA    339          NOP          ;
6016:EA    340          NOP          ;
6017:EA    341          NOP          ;

6018:EA    343          NOP          ;
6019:EA    344          NOP          ;
601A:EA    345          NOP          ;
601B:EA    346          NOP          ;
601C:EA    347          NOP          ;
601D:EA    348          NOP          ;
601E:EA    349          NOP          ;
601F:EA    350          NOP          ;
```



## PROGRAM RM-0, CONT'D . . .

```
6020:          353 ;          *** LITTLE LUMPS ***
6020:          354 ;          *** HEAVY SUBROUTINE ***
6020:          355 ;          *** SUPPORTING MODULE ***

6020:          357 ;          ADD ANY COMMENTS HERE THAT ARE
6020:          358 ;          SPECIFIC TO THE LITTLE LUMPS.
6020:          359 ;
6020:          360 ;
6020:          361 ;
6020:          362 ;

6020:EA        364 START2  NOP          ; YOUR MEDIUM LEVEL CODE STARTS
6021:EA        365          NOP          ; HERE AND GOES ON AS FAR AS
6022:EA        366          NOP          ; NEEDED.
6023:EA        367          NOP          ;
6024:EA        368          NOP          ;
6025:EA        369          NOP          ;
6026:EA        370          NOP          ;
6027:EA        371          NOP          ;

6028:EA        373          NOP          ;
6029:EA        374          NOP          ;
602A:EA        375          NOP          ;
602B:EA        376          NOP          ;
602C:EA        377          NOP          ;
602D:EA        378          NOP          ;
602E:EA        379          NOP          ;
602F:EA        380          NOP          ;

6030:EA        382          NOP          ;
6031:EA        383          NOP          ;
6032:EA        384          NOP          ;
6033:EA        385          NOP          ;
6034:EA        386          NOP          ;
6035:EA        387          NOP          ;
6036:EA        388          NOP          ;
6037:EA        389          NOP          ;

6038:EA        391          NOP          ;
6039:EA        392          NOP          ;
603A:EA        393          NOP          ;
603B:EA        394          NOP          ;
603C:EA        395          NOP          ;
603D:EA        396          NOP          ;
603E:EA        397          NOP          ;
603F:EA        398          NOP          ;
```

## PROGRAM RM-0, CONT'D . . .

```
6040:      401 ;          *** STASH ***
6040:      402 ;          *** THE CRUMBS ***
6040:      403 ;          *** DETAIL SUBS ***

6040:      405 ;          ADD ANY COMMENTS HERE THAT
6040:      406 ;          ARE SPECIFIC TO THE CRUMBS.
6040:      407 ;
6040:      408 ;
6040:      409 ;
6040:      410 ;

6040:EA    412 START3  NOP          ; YOUR LOW LEVEL CODE STARTS HERE AND
6041:EA    413          NOP          ; INCLUDES ANY SHORT FILES THAT ARE
6042:EA    414          NOP          ; RARELY CHANGED.
6043:EA    415          NOP          ;
6044:EA    416          NOP          ;
6045:EA    417          NOP          ;
6046:EA    418          NOP          ;
6047:EA    419          NOP          ;

6048:EA    421          NOP          ;
6049:EA    422          NOP          ;
604A:EA    423          NOP          ;
604B:EA    424          NOP          ;
604C:EA    425          NOP          ;
604D:EA    426          NOP          ;
604E:EA    427          NOP          ;
604F:EA    428          NOP          ;

6050:EA    430          NOP          ;
6051:EA    431          NOP          ;
6052:EA    432          NOP          ;
6053:EA    433          NOP          ;
6054:EA    434          NOP          ;
6055:EA    435          NOP          ;
6056:EA    436          NOP          ;
6057:EA    437          NOP          ;

6058:EA    439          NOP          ;
6059:EA    440          NOP          ;
605A:EA    441          NOP          ;
605B:EA    442          NOP          ;
605C:EA    443          NOP          ;
605D:EA    444          NOP          ;
605E:EA    445          NOP          ;
605F:EA    446          NOP          ;
```

## PROGRAM RM-0, CONT'D . . .

```

6060:          449 ;          *** MAIN FILES ***

6060:          451 ;          ADD ANY COMMENTS HERE THAT ARE
6060:          452 ;          SPECIFIC TO THE MAIN FILES.
6060:          453 ;
6060:          454 ;
6060:          455 ;
6060:          456 ;

6060:00 00 00 458 FILE1  DFB          $00,$00,$00,$00,$00,$00,$00,$00
6063:00 00 00
6066:00 00
6068:00 00 00 459 FILE2  DFB          $00,$00,$00,$00,$00,$00,$00,$00
606B:00 00 00
606E:00 00
6070:00 00 00 460 FILE3  DFB          $00,$00,$00,$00,$00,$00,$00,$00
6073:00 00 00
6076:00 00
6078:00 00 00 461 FILE4  DFB          $00,$00,$00,$00,$00,$00,$00,$00
607B:00 00 00
607E:00 00
6080:00 00 00 462 FILE5  DFB          $00,$00,$00,$00,$00,$00,$00,$00
6083:00 00 00
6086:00 00
6088:00 00 00 463 FILE6  DFB          $00,$00,$00,$00,$00,$00,$00,$00
608B:00 00 00
608E:00 00
6090:00 00 00 464 FILE7  DFB          $00,$00,$00,$00,$00,$00,$00,$00
6093:00 00 00
6096:00 00
6098:00 00 00 465 FILE8  DFB          $00,$00,$00,$00,$00,$00,$00,$00
609B:00 00 00
609E:00 00
60A0:00 00 00 466 FILE9  DFB          $00,$00,$00,$00,$00,$00,$00,$00
60A3:00 00 00
60A6:00 00
60A8:00 00 00 467 FILE10 DFB          $00,$00,$00,$00,$00,$00,$00,$00
60AB:00 00 00
60AE:00 00
60B0:00 00 00 468 FILE11 DFB          $00,$00,$00,$00,$00,$00,$00,$00
60B3:00 00 00
60B6:00 00
60B8:00 00 00 469 FILE12 DFB          $00,$00,$00,$00,$00,$00,$00,$00
60BB:00 00 00
60BE:00 00
60C0:00 00 00 470 FILE13 DFB          $00,$00,$00,$00,$00,$00,$00,$00
60C3:00 00 00
60C6:00 00
60C8:00 00 00 471 FILE14 DFB          $00,$00,$00,$00,$00,$00,$00,$00
60CB:00 00 00
60CE:00 00

```

## PROGRAM RM-0, CONT'D . . .

60D0:00 00 00	474 FILE15	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
60D3:00 00 00			
60D6:00 00			
60D8:00 00 00	475 FILE16	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
60DB:00 00 00			
60DE:00 00			
60E0:00 00 00	476 FILE17	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
60E3:00 00 00			
60E6:00 00			
60E8:00 00 00	477 FILE18	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
60EB:00 00 00			
60EE:00 00			
60F0:00 00 00	478 FILE19	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
60F3:00 00 00			
60F6:00 00			
60F8:00 00 00	479 FILE20	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
60FB:00 00 00			
60FE:00 00			
6100:00 00 00	480 FILE21	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
6103:00 00 00			
6106:00 00			
6108:00 00 00	481 FILE22	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
610B:00 00 00			
610E:00 00			
6110:00 00 00	482 FILE23	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
6113:00 00 00			
6116:00 00			
6118:00 00 00	483 FILE24	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
611B:00 00 00			
611E:00 00			
6120:00 00 00	484 FILE25	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
6123:00 00 00			
6126:00 00			
6128:00 00 00	485 FILE26	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
612B:00 00 00			
612E:00 00			
6130:00 00 00	486 FILE27	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
6133:00 00 00			
6136:00 00			
6138:00 00 00	487 FILE28	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
613B:00 00 00			
613E:00 00			
6140:00 00 00	488 FILE29	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
6143:00 00 00			
6146:00 00			
6148:00 00 00	489 FILE30	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
614B:00 00 00			
614E:00 00			
6150:00 00 00	490 FILE31	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
6153:00 00 00			
6156:00 00			
6158:00 00 00	491 FILE32	DFB	\$00,\$00,\$00,\$00,\$00,\$00,\$00,\$00
615B:00 00 00			
615E:00 00			

**PROGRAM RM-0, CONT'D . . .**

**6160:            494 ;            \*\*\* BOTTOM LINE COMMENTS \*\*\***

**6160:            496 ;            ADD ANY FINAL COMMENTS YOU FEEL**  
**6160:            497 ;            ARE NEEDED IN THIS SPACE.**

**\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS**

## FILE BASED PRINTER

**the “standard” way to output short and fixed text messages by using a common message file.**

Outputting text is probably the most fundamental and most important task we would ever ask of a machine language Apple program. You might want to use the text to create a printed record, to inform the user via the video screen, or to pass a command to the disk system.

It turns out that there is no “best” way to go about outputting text from machine language. Instead, there are many different methods you can pick. These methods are based on *how many* messages you must output, on *how long* each message is, and on *how changeable* the messages have to be.

Further, you have to decide just *where* your message is going to go as well. Usually, to output a character, you get it from somewhere and put it in the accumulator. Then you go to a text outputting subroutine that puts the character where you want it to appear. You continue this until some change occurs, such as a marker or length count. Then you go on to the next task at hand.

Here are some possible . . .

PLACES TO OUTPUT TEXT
Direct store to the text screen To COUT hook subroutine \$FDF0 To COUT1 screen subroutine \$FDED To a HIRES character generator To your own custom code

If you *direct store* to a screen location, you end up putting characters on the screen in the shortest possible time, and you are always sure *exactly* where on the screen the character is to go. As an example, a \$C1 stored in \$0400 puts an uppercase "A" in the upper left-hand screen position. But, the screen locations aren't mapped in an obvious order, and you get into real hassles over carriage returns and scrolls. There is also no simple way to get a hard copy of a direct screen store. So, direct storing to the screen is usually limited to game scores, status lines, and special effects, rather than being a mainstream way of doing things.

Since outputting text is so important, there are two subroutines built into the Apple's monitor, designed to do most text outputting tasks in the way that most people want them done. One subroutine is called COUT and is located at \$FDED. This subroutine will output characters to anything that is connected to the Apple by way of two *character hooks* called CSWL and CSWH and located at \$0036 and \$0037.

Normally, DOS grabs these character hooks so that it can intercept all output commands, just in case there is something intended for the disk. In turn, DOS will take whatever was plugged into the output hooks, and then plug these into itself.

For instance, a normal hard copy character will get routed from your code to COUT, where it gets passed on to DOS, which checks it for disk commands. The character is then passed on to a printer card, whose code often begins at location \$C100. The code will then send the proper commands to the printer itself to print the character. Finally, if you want it to, the printer card code will echo the character on to the screen subroutine.

Which is very slow and roundabout. But this is the standard way of outputting characters that can be routed to DOS, a printer, the screen, or anywhere else you like. This process is extremely slow on the IIe when 80-column firmware is in use. So slow in fact, that you cannot keep up with a 1200-baud modem and scroll the screen at the same time.

The actual *screen subroutine* that puts the characters on the screen is called COUT1 and sits at \$FDF0. Good old "Fideyfoo." Fideyfoo automatically keeps track of the horizontal and vertical character positions, does scrolls, handles carriage returns, inverses, your choice of flashing or lowercase, and takes care of most screen actions in the way that most people want most of the time.

Fideyfoo has some locations on page zero reserved that let you pick up special effects quickly and simply. For instance, the size of the scrolling window is set by locations \$20 through \$24. The cursor hori-

zontal and vertical position bytes CH and CV are located at \$24 and \$25. Your choice of normal/inverse/flash is decided by INVFLG at \$31. And the screen prompt is stashed in \$33. See the EMPTY SHELL.SOURCE hooks for other locations of interest.

Here's how to remember when to use COUT or COUT1 . . .

**Use COUT at \$FDED to slowly output a character to DOS, a printer, the screen, or anywhere else you want to send that character. Hooks CSWL and CSWH at \$36 and \$37 decide where the character is to go.**

**Use COUT1 at \$FDF0 to rapidly output a character only to the screen.**

By the way, all these fancy subroutines do take time. It can take half a millisecond just to get through COUT and the DOS code, and any screen scrolls can hold up the works for four or more milliseconds. These times are on older Apples; the IIe is much worse in its 80-column mode. So, it pays to go directly to the screen or output device if speed is important.

It also pays to defeat any "screen echo" should you need top output speed. For instance, a HIRES graphics hard copy dump will be dramatically slowed down if it has to wait for screen scrolling on echo. For fastest possible speed, DOS could also be disconnected during character output times. And fast modems are best used on a IIe in its 40-column or "no-display" modes.

A third place to put your characters involves using a *HIRES character generator* to put your characters onto the HIRES screen. This type of subroutine lets you mix and match graphics and lets you use lots of different text fonts of varying sizes. You can also use special characters to do animation with a HIRES character generator, since your letter "G" is free to look like a frog's face, rather than a stock character. But HIRES character generators are usually rather slow and take bunches of extra code inside your machine.

Normally, a HIRES character generator will grab the COUT hooks "behind" DOS. Its use, once installed, will be pretty much the same as using COUT. Naturally, a HIRES character generator only will display on a HIRES screen and COUT1 will only display on a text screen.

A final place to put characters is to route them to your own custom code subroutine. This lets you rearrange things to suit yourself. A word processor is one example, where the messages all change from use to use. A second example could be a special effects screen filter. This one could "print" in oddball directions, and include delay, sound effects, replacements, screen locking, whole-word breaks, column justify, and most anything else you'd care to dream up.

Normally, you should avoid writing your own code if it more or less duplicates what is already available as ready-to-go subroutines in the Apple monitor. But special code can do special things special ways, and sometimes can give you a tremendous programming advantage over competitive programs.

An edge, even.

So, your first problem is to decide where your text is going to go.



Then, you have to pick some method of getting text to that destination.

Here are the names of several more popular text outputting methods, going from simple to complex . . .

TEXT OUTPUTTING SCHEMES
Brute Force Short File Long File Imbedded Text Compacted

The *brute force* method is simple and obvious. "Give me a D!" "Give me an O!" "Give me a G!" And whaddaya got? A doggedly cumbersome and very painful way to output text. Load the accumulator with the ASCII character for a D and then JSR your output code. Then load the accumulator with an ASCII "O," and so on.

This method is so painful, that you would only want to use it for a four-letter or shorter message, and then if that message was the only one in the program. Among other problems, note that five bytes of code are needed per character output.

The *short file* method is almost as obvious as the brute force method. Put your characters in a file. End each message with some marker, say an ASCII \$00 or NUL. If you have to, create a second *pointer* file to tell you where each message starts. The short file is usually limited to 256 or fewer total characters.

The short file method uses indexed addressing to pick sequential characters out of a file. For a detailed example, see the text outenblatter in Volume II of *Don Lancaster's Micro Cookbook* (Sams 21829). Just for kicks, we will also use the short file method in the card shuffler of Ripoff Module 8.

The short file method is limited to a few very short and fixed text messages. But it is quick and simple to program, and may be all you need.

The *long file* method removes the 256 character restriction, by replacing 8-bit indexed loads with 16-bit indirect indexed loads. Your messages can now be any length and you can have any number of them, although there is a slight complication for more than 128 *different* messages at any time.

The long file method is more or less the "standard" way of handling medium length text messages, and is what this ripoff module is all about. We'll find out how your assembler can automate keeping track of messages and message pointers, as well as automatically entering ASCII characters for you.

But, there are limits to the long file method. All your messages must be known and all must be placed at one point in your code. The *imbedded text* method of the next ripoff module very elegantly gets around these restrictions, by letting you put any message you want, any place you want, *directly in your source code*. You can mix and match messages from any modules in your program, so long as one "un-imbedding" subroutine is provided somewhere in your code.

Both the long file and the imbedded text methods take around a byte per character for longer messages. You can remove the end marker on each string message if you switch from high ASCII to low ASCII on the last character. EDASM can do this for you as a special feature. But this complication doesn't save you very much, particularly on longer messages. You can also use a character count byte if you like. Again, this doesn't help much.

Should you have to really cram long messages into your Apple, you can either use repeated disk access or else use some *text compaction* scheme. Repeated disk access is very poor form these days and should be avoided, even with the newer DOS speedup tricks. Text compaction works by using some non-ASCII code that is more efficient than ASCII for character storage.

For instance, in the *Zork* adventures, three characters are crammed into two bytes, giving you code that needs only 67 percent of the space needed by ASCII. In the Adam's version of *Collossial Cave*, letters are arranged into pairs and then each pair is given an unique code. This results in nearly a 50 percent compaction. In spelling checkers, special codes are used to tell how many characters have not changed from the previous character. Special codes are also used for stock endings.

In general, you should not use text compaction until after you are sure you absolutely must have it. It's usually best to have your code completely debugged and your messages completely fixed before using compaction. Note that text compaction will actually *lengthen* and complicate the code needed for short messages, so there is some minimum "breakeven" code length before compaction gains you anything at all.

To recap, there are many places you can put characters and many different ways to generate text messages. One standard way is the text file method, which we will look at here. After that, in Ripoff Module 2, we will check into a more elegant imbedded text method that often is a better choice. Either of these methods is a good choice for your typical "medium" text message jobs, those not so trivial and short that you can handle with obvious code, nor those messages so long that you have to compact them.

So, without further ado, here is . . .


## THE LONG FILE METHOD

There are two files involved in the long file method. One of these is called the *pointer file* and the other is called the *message file* . . .

## USING A PAIR OF FILES TO OUTPUT TEXT STRINGS:

THE **POINTER FILE** HOLDS THE 16-BIT STARTING ADDRESS OF EACH TEXT MESSAGE IN THE MESSAGE FILE. . .

THE **MESSAGE FILE** HOLDS ALL OF THE ASCII TEXT MESSAGES IN SOME KNOWN ORDER. . .



. . . MESSAGES CAN BE ACCESSED IN ANY ORDER. MORE THAN ONE POINTER CAN POINT TO THE SAME MESSAGE. EACH MESSAGE CAN BE ANY LENGTH.

The long file method seems complicated at first, but this text outputting scheme lets you have messages of any length, and the messages can easily cross 256-byte page boundaries. You can also use different sets of pointer files and text files with the same FLPRINT subroutine.

The message file holds all the messages. The messages do not have to be in any particular order, but the order must be known. Each message ends with a marker of some sort. We will use an ASCII double zero NUL command, since it is easier to test for zero than for any other value. Normally, each message will follow the previous one, although this is not essential. Should you want to put a DOS message into your message file, you start the DOS message with a carriage return and a [D], or "<CTRL> D," otherwise known as an ASCII CR and EOT.

The pointer file holds a list of addresses that show the start of each message. Note that each pointer has to be a 16-bit, or two-byte, address, since the message file can be many pages long. Each pointer file is thus limited to 128 different message pointers, but you can have as many pointer files in your program as you like.

As you might guess, it can be a real drag building and connecting your files by hand. We will show you a fully automatic way to let your assembler build and link files for you. It's all done with creative use of labels.

To use the long file method, you first pick a pointer file. Then you decide which message you want. Say it is message 2. Then you read the pointer file to find the start of the message, say \$441F. Then you reach into the message file, starting at \$441F, get a character, and then output that character. You continue the process one character at a time till the marker comes up. Then you quit.

The messages do not have to be in any special order, and you can let several different pointers lead you to the same message. This gets handy for prompts like "Please make another selection;" or "That's not a letter, turkey!" defaults or error traps. You also can start at the *middle* of another message, and read to the end. This trick can sometimes save you space by using words over again.

The tricky part is being able to read long messages that cross page boundaries. To do this, you use the powerful 6502 indirect indexed command. In this ripoff module, we will set aside a pair of page zero address locations at \$EB and \$EC. When we decide to output a message, you reach into the pointer file and put the low half of the message starting address into \$EB, and the high half of the message start into \$EC.


Then, you set your Y register to #00, and use the LDA(\$EB),Y indexed indirect addressing instruction. What this command does is go to the sum of the 16-bit address in \$EB and \$EC (the start of your message) *plus* the Y register value (zero) to get the character to be output.

After the first character, you have a choice. You could increment Y to get to the next character, or else you could add one to the \$EB,EC pair. While adding one to Y seems faster and more attractive at first, this will only let you have 256 characters in any one message. So, we will keep Y at zero, and increment the base address. To increment a base address, you first increment the low byte at \$EB. If you get a zero result, you then also increment the high byte at \$EC. This way, you can continually work your way through most of the 64K address space, without any worries about page boundaries or running out of 8-bit range.

Holding the Y register at zero during an indexed indirect load simply "downgrades" the load command into a straight indirect load. Incidentally, the new 65C02s have "pure" or "unindexed" indirect commands that free up the Y register for other uses.

Confused? Here's a flowchart . . .

**FLPRINT FLOWCHART:**



Let's check into the actual code of the FLPRINT module, sitting at \$624B. This is the module that outputs the text messages for you, and is what you will want to adapt to your own needs.

One good starting place to analyze any code is to find out where variables are stashed. On FLPRINT, we set aside two page zero locations at \$EB and \$EC to point to the start of our pointer file. These we call PFP1 and PFP1+1. We set aside two more locations at \$ED and \$EE to use as a running character pointer that works through the message file. These two are labeled MSP1 and MSP1+1.

We also provide a short stash at the end of the subroutine. Three locations here are used for a temporary Y register save YSAV1, an X

register save XSAV1 and a total number-of-messages value at MNUM1.

You enter this FLPRINT module with the message number in the accumulator. You also must have pre-placed the pointer file starting address in PFP1.

We first save the X and Y registers into temporary stashes at XSAV1 and YSAV1. Next, you run a range check of the message number against the stash at MNUM1. A range check makes sure the message is a legal one. This keeps you from outputting garbage or plowing up a disk. We have used a MNUM1 value of \$10, good for 16 separate messages.

If the message number is illegal, you restore the X and Y registers and exit without doing anything else. In a "real" program, you would error trap this and do something about it instead.

If the message number is valid, you double it with an ASL, since you are after *pairs* of addresses in the pointer file, each of which takes up 2 bytes.

Then, you reach into the pointer file and get the low half of the address and stash it at MSP1 and then grab the high half and dump it into MSP1+1. We knew *which* pointer file to go to, since whatever code that JSRed here put the pointer file starting address into PFP1 ahead of time.

At this point in the subroutine, we have placed an address into MSP1 and MSP1+1 that points to the first character in the desired message. Now, it's up to the service loop called NXTCHR1 to handle characters for us. NXTCHR1 first grabs a character. If that character was a double zero, the loop quits and exits via END1. This is how you end a message.

Usually, though, the character that NXTCHR1 grabs is not a double zero, so NXTCHR1 passes the character out to the Apple monitor subroutine at COUT that sends the character to whatever is connected to the output hooks.

Typically, the "hooked " character may go through DOS, which checks it for a [return] [D] header. If it doesn't look like something DOS is interested in, DOS then passes the character somewhere else, possibly to a printer card whose code may start at \$C100. The printer card will send the character to a printer, and, optionally, will pass it on to the screen subroutine \$FDF0 at COUT1.

None of which matters to NXTCHR1, for once this loop outputs a character to COUT, it couldn't care less what happens to the character. After the character is sent to wherever it is supposed to go, COUT returns control back to NXTCHR1 via a RTS subroutine return.

NXTCHR1's next job is to move the message file character pointer MSP1 over to the next character. Since this pointer is 16 bits wide, the low byte at MSP1 is first incremented. Should we get a zero result, indicating that a carry is needed to the high byte, we then increment the high byte. This is a pretty much standard way of incrementing a 16-bit address pointer pair.

Following that, we jump back to the start of the NXTCHR1 loop and keep outputting characters till we hit the double zero.

Note the forced branch at NOC1. It pays to keep absolute jumps out of any of your code modules, for absolute references make code harder to relocate. The CLC and BCC commands together do an unconditional relative branch for you that is easily relocatable.

After the double zero, we get out of the FLPRINT subroutine by restoring the X and Y registers and doing the usual RTS back to whoever it was that JSRed this module.

The DEMO1 that starts at \$6200 is a rather unexciting "exerciser" that shows us how FLPRINT works. DEMO1 first sets the total number of messages to \$03 and then finds out where the message pointer file sits. It then stores the pointer file start in MSP1, for use by FLPRINT.

Then we clear the screen, do some tabbing, and go to the inverse mode. Message #00 is called for, and gotten through FLPRINT. We return to normal text for message #01. Note that message #02 is quite long. It could, in fact, be any length you want, within the limits of available memory.

After message #01, we ask for user input. Should we get an "E," we exit the program. A "C" gives you a DOS catalog. This is done by printing first a CR and then an EOT, or [D], followed by the CATALOG string. If the CATALOG is long enough, extra prompts are needed for each catalog page.

Should you enter anything but an "E" or a "C," the entire FLPRINT module is rerun. This error trapping causes a brief flash on the screen, which should be enough of an operator "hey turkey!" prompt for most users.

In this example, we require a capital C or capital E. It is better practice to allow for either uppercase or lowercase entries. You can do this with a double test, or else by forcing lowercase characters into their uppercase equivalents. This important detail should not be omitted on the IIe or for older uses where you expect mixed cases. You'll find a case changer example in Ripoff Module 7.

Note that both the pointer file and the message file can be repeatedly reloaded off the disk. Thus, there is no limit to using external or calculated text strings as might be needed in a longer adventure.

## Creating the Files

A good assembler will very much simplify setting up and creating your own pointer and text files. The process of putting the file into memory and properly linking it with everything else can be made fully automatic, without any worries about absolute addresses.

It's labels to the rescue.

Let's look at the message file first. First and foremost, you put a label at the beginning of each separate message. We have used M1.0 through M1.15 in the source code. If you have a label on your message, your assembler can find the message, regardless of where it ends up in memory.

We stopped at sixteen messages only to save on source code length. You can make things as long as you like, with up to 128 messages for each message pointer file and as many message pointer files as you want.

The ASC and DFB commands greatly simplify entering your messages. We've done almost everything here in uppercase for compatibility with older Apples, but most newer assemblers will let you use full case for your messages. "New way" editing also lets you do lowercase on most any assembler.

The ASC command tells the assembler to "convert what follows to ASCII." High ASCII is normally used in the Apple, although you can

---

change this if you want to. While each ASCII string can be any length, it pays to keep each string under 32 characters or so. This makes for neater assembly listings. You can tie as many strings together as you need to get the total message.

A delimiter should start the ASCII text string. Use a quote for the delimiter unless you really want to print a quote. Then use a slash instead. An ending delimiter is not needed if there are no comments on the string line. Usually there won't be room for comments anyway, so this is no big deal. This is roughly similar to not needing the final quote in an Applesoth PRINT statement. Trailing spaces are hard to see without a final delimiter.

So much for alphanumerics. How do you handle control characters?

Obviously, you need a way to, say, imbed carriage returns. Yet if you type a carriage return, the string command completes itself. How do you get out of this bind?

Once again, it's labels to the rescue. Just as you can use a CHR\$(13) to fool a higher level language into outputting a carriage return, you can trick an assembler into entering a carriage return into a file by using a label.

I've chosen to use single letter labels for control commands. B for backspace, C for carriage return, D for DOS, and X for the NULL or double zero. Each letter must be pre-defined as a constant, such as a B EQU \$88 for a backspace. To enter control commands into your ASCII text, simply use DFBs with as many control commands as you like.

For instance, a DFB C,X puts a carriage return and an end-of-text marker into your message file. That wild DFB B,B,B,P,B,X sequence uses backspaces to center a flashing user prompt inside a fancy screen symbol. Incidentally, this may look different on a II and Iie. You might like to change it per the Apple in use.

Unfortunately, this was written before "new" EDASM became available. Since "A," "X," and "Y" are disallowed labels in "new" EDASM, you'll have to substitute something else for "X." Note that the STR pseudo-op in "new" EDASM can eliminate any need for a trailing NULL.

Summing up our message file, be sure to put a label on the start of each message. Then enter your ASCII characters using the assembler's ASC command. Don't forget the delimiter at the front and don't let the individual ASC strings get too long. Enter any control characters you want to imbed with DFB commands. On a typical message, you will alternate ASC and DFB commands. Use ASC for the letters and DFB for the carriage returns and end markers.

The pointer file will usually be much shorter than the message file. The pointer file holds the starting address of each message, so that FLPRINT knows where to go to start outputting characters.

To automate the construction of a pointer file, just use labels for each pointer entry. For instance, we call the pointer to the sixth message PF5 (don't forget that zero!). Our pointer source code under label PF5 tells us to DW M1.5, or to "go to wherever the message labeled M1.5 happens to be, find its present absolute address, and put that address pair back here."

Which is an awful lot of work for the assembly program. But that's its job and is one of the many reasons why we use an assembler in the first place—to automate most of the dogwork involved in writing machine language programs.



**MIND BENDERS**

- Show how FLPRINT can be simplified if you only have one pointer file in your program.
- FLPRINT works fine when called from *within* another program, but there's a slight bug when used directly from the monitor or Applesoft. What is the bug? What causes it? How can you prevent it?
- How can you design a program that outputs lowercase only to those machines that can use it?
- Can FLPRINT be used with changing messages? How?
- Show ways to use FLPRINT with several different pointer files.
- Rewrite this module to use "new" EDASM's string command STR, which includes a message count byte. What are the advantages of this new method?

**PROGRAM RM-1  
FILE BASED PRINTER**

----- NEXT OBJECT FILE NAME IS FLPRINT

6200:           3           ORG \$6200           ; PUT MODULE #1 AT \$6200

```

6200:           5 ; *****
6200:           6 ; *
6200:           7 ; *           -< FLPRINT MODULE >-           *
6200:           8 ; *
6200:           9 ; *           (FILE BASED STRING PRINTER)       *
6200:          10 ; *
6200:          11 ; *           VERSION 1.0 ($6200-$642A)       *
6200:          12 ; *
6200:          13 ; *           6-15-83                           *
6200:          14 ; * .....*
6200:          15 ; *
6200:          16 ; *           COPYRIGHT C 1983 BY           *
6200:          17 ; *
6200:          18 ; *           DON LANCASTER AND SYNERGETICS   *
6200:          19 ; *           BOX 1300, THATCHER AZ., 85552   *
6200:          20 ; *
6200:          21 ; *           ALL COMMERCIAL RIGHTS RESERVED   *
6200:          22 ; *
6200:          23 ; *****

```

6200:           25 ;           \*\*\* WHAT IT DOES \*\*\*

```

6200:           27 ;       THIS MODULE OUTPUTS TEXT STRINGS OR DOS COMMANDS
6200:           28 ;       TO THE APPLE II'S OUTPUT HOOKS, USING STRINGS
6200:           29 ;       THAT ARE COLLECTED TOGETHER IN A COMMON FILE.
6200:           30 ;
6200:           31 ;
6200:           32 ;

```

6200:           34 ;           \*\*\* HOW TO USE IT \*\*\*

```

6200:           36 ;       YOUR CALLING CODE SHOULD HAVE PREVIOUSLY STORED
6200:           37 ;       A MESSAGE POINTER FILE ADDRESS IN PFP1 (LOW) AND
6200:           38 ;       PFP1+1 (HIGH). ONE OF 128 POSSIBLE RESPONSES
6200:           39 ;       ARE SELECTED BY LOADING THE ACCUMULATOR WITH A
6200:           40 ;       MESSAGE NUMBER AND THEN DOING A JSR TO FLPRINT.
6200:           41 ;

```

## PROGRAM RM-1, CONT'D . . .

```
6200:      44 ;          *** GOTCHAS ***

6200:      46 ; THIS METHOD IS BEST USED FOR LONG MESSAGES THAT MIGHT
6200:      47 ; NEED CALCULATED VALUES OR DISK-BASED CHANGES.
6200:      48 ;
6200:      49 ; MESSAGES CAN BE ANY LENGTH, BUT MORE THAN 128 DIFFERENT
6200:      50 ; MESSAGES WILL NEED SEPARATE MSP1 ADDRESS BASES. EACH
6200:      51 ; MESSAGE MUST END IN A $00 MARKER.

6200:      53 ;          *** ENHANCEMENTS ***

6200:      55 ; DOS COMMANDS ARE OUTPUT BY STARTING THE STRING
6200:      56 ; WITH A CARRIAGE RETURN AND <CTRL> D.
6200:      57 ;
6200:      58 ; TO GO DIRECTLY TO THE SCREEN, USE COUT1 RATHER THAN COUT.
6200:      59 ; THIS IS FASTER, BUT CANNOT CONTROL DOS OR BE PRINTED.
6200:      60 ;

6200:      62 ;          *** RANDOM COMMENTS ***

6200:      64 ; TO RUN THE DEMO, USE $6200G OR CALL 25088.
6200:      65 ;
6200:      66 ; THE X AND Y REGISTERS ARE PRESERVED; A IS DESTROYED.
6200:      67 ;
6200:      68 ;
6200:      69 ;
```

## PROGRAM RM-1, CONT'D . . .

```
6200:          72 ;          *** HOOKS ***

FDED:          74 COU     EQU  $FDED    ; OUTPUT CHARACTER VIA HOOKS
FC58:          75 HOME    EQU  $FC58    ; CLEAR SCREEN
FB2F:          76 INIT    EQU  $FB2F    ; INITIALIZE TEXT SCREEN
C010:          77 KBDSTR  EQU  $C010    ; KEYBOARD RESET
F94A:          78 PRBL2   EQU  $F94A    ; PRINT X BLANKS
FD0C:          79 RDKEY   EQU  $FD0C    ; GET INPUT CHARACTER
FE80:          80 SETINV  EQU  $FE80    ; SET INVERSE SCREEN
FE84:          81 SETNORM EQU  $FE84    ; SET NORMAL SCREEN

00ED:          83 MSP1    EQU  $ED      ; MESSAGE FILE CHARACTER POINTER
00EB:          84 PFPL    EQU  $EB      ; POINTER FILE STARTING ADDRESS

6200:          86 ;          *** TEXTFILE COMMANDS ***

0088:          88 B       EQU  $88      ; BACKSPACE
008D:          89 C       EQU  $8D      ; CARRIAGE RETURN
0084:          90 D       EQU  $84      ; DOS ATTENTION
0060:          91 P       EQU  $60      ; FLASHING PROMPT
0000:          92 X       EQU  $00      ; END OF MESSAGE
```

## PROGRAM RM-1, CONT'D . . .

```

6200:          95 ;          *** DEMO ***
6200:          96 ;

6200:          98 ;          THE DEMO USES THE FLPRINT MODULE TO OUTPUT
6200:          99 ;          SCREEN MESSAGES AND A DOS CATALOG COMMAND.
6200:          100 ;

6200:A9 03      102 DEMO1   LDA  #$03      ; THREE MESSAGES TOTAL
6202:8D 7D 62   103       STA  MNUM1     ; SAVE FOR CHECK
6205:A9 80      104       LDA  #>PF0     ; SAVE MESSAGE POINTER LOW
6207:85 EB      105       STA  PFP1      ;
6209:A9 62      106       LDA  #<PF0     ; SAVE MESSAGE POINTER HIGH
620B:85 EC      107       STA  PFP1+1    ;

620D:20 2F FB   109       JSR  INIT      ; GO TO TEXT MODE
6210:20 58 FC   110       JSR  HOME      ; CLEAR SCREEN
6213:A2 08      111       LDX  #$08      ; PRINT BLANKS VIA MONITOR
6215:20 4A F9   112       JSR  PRBL2     ;

6218:20 80 FE   114       JSR  SETINV    ; INVERSE TEXT FOR TITLE
621B:A9 00      115       LDA  #00      ; MESSAGE #0
621D:20 4E 62   116       JSR  FLPRINT   ; PRINT MESSAGE

6220:20 84 FE   118       JSR  SETNORM   ; NORMAL TEXT
6223:A9 01      119       LDA  #$01      ; MESSAGE #1
6225:20 4E 62   120       JSR  FLPRINT   ; PRINT MESSAGE

6228:2C 10 C0   122       BIT  KBDSTR    ; RESET KEYBOARD
622B:20 0C FD   123       JSR  RDKEY     ; GET KEY
622E:C9 C5      124       CMP  #$C5     ; AN "E" FOR EXIT?
6230:F0 15      125       BEQ  EXIT1     ; YES, EXIT
6232:C9 C3      126       CMP  #$C3     ; A "C" FOR CATALOG?
6234:D0 CA      127       BNE  DEMO1     ; TRY AGAIN FOR VALID KEY

6236:20 58 FC   129       JSR  HOME      ; CLEAR SCREEN, THEN
6239:A9 02      130       LDA  #$02     ; DO CATALOG
623B:20 4E 62   131       JSR  FLPRINT   ;
623E:2C 10 C0   132       BIT  KBDSTR    ; HOLD CATALOG
6241:20 0C FD   133       JSR  RDKEY     ; TILL KEYPRESS

6244:18          135       CLC          ; BRANCH ALWAYS
6245:90 B9      136       BCC  DEMO1     ; AND TRY AGAIN

6247:20 58 FC   138 EXIT1   JSR  HOME      ; EXIT DEMO
624A:2C 10 C0   139       BIT  KBDSTR    ; RESET KEYBOARD
624D:60          140       RTS          ;

```

## PROGRAM RM-1, CONT'D . . .

```

624E:      143 ;          *** FLPRINT MODULE ***
624E:      144 ;
624E:      145 ;

624E:      147 ;          THIS MODULE USES THE ACCUMULATOR VALUE TO
624E:      148 ;          FIND A POINTER TO THE TEXT STRING. IT THEN
624E:      149 ;          OUTPUTS ONE CHARACTER AT A TIME TILL THE $00
624E:      150 ;          END-OF-MESSAGE MARKER IS FOUND.
624E:      151 ;
624E:      152 ;

624E:8C 7F 62 154 FLPRINT STY  YSAV1      ; SAVE REGISTERS
6251:8E 7E 62 155          STX  XSAV1      ;

6254:CD 7D 62 157          CMP  MNUM1      ; A LEGAL MESSAGE NUMBER?
6257:B0 1D          158          BCS  ENDL      ; DON'T PRINT IF ILLEGAL
6259:0A          159          ASL  A          ; DOUBLE POINTER FOR ADDRESS PAIR
625A:A8          160          TAY          ;
625B:B1 EB          161          LDA  (PFPL),Y ; GET LOW POINTER
625D:85 ED          162          STA  MSP1      ; AND SAVE
625F:C8          163          INY          ;
6260:B1 EB          164          LDA  (PFPL),Y ; GET HIGH POINTER
6262:85 EE          165          STA  MSP1+1    ; AND SAVE
6264:A0 00          166          LDY  #$00      ; NO INDEXING
6266:B1 ED          167 NXCWRL LDA  (MSP1),Y ; GET CHARACTER
6268:F0 0C          168          BEQ  ENDL      ; EXIT ON $00 MARKER
626A:20 ED FD          169          JSR  COUT      ; PRINT CHARACTER

626D:E6 ED          171          INC  MSP1      ; CALCULATE NEXT CHARACTER LOCATION
626F:D0 02          172          BNE  NOC1      ; IF A CARRY, THEN
6271:E6 EE          173          INC  MSP1+1    ; INCREMENT HIGH ADDRESS LOCATION
6273:18          174 NOC1      CLC          ; BRANCH ALWAYS TO
6274:90 F0          175          BCC  NXCWRL    ; GET NEXT CHARACTER

6276:AE 7E 62 177 ENDL      LDX  XSAV1      ; RESTORE REGISTERS
6279:AC 7F 62 178          LDY  YSAV1      ;
627C:60          179          RTS          ; AND EXIT

627D:      181 ;          *** STASH ***

627D:10          184 MNUM1      DFB  $10      ; NUMBER OF MESSAGES IN FILE
627E:00          185 XSAV1      DFD  $00      ; X-REGISTER SAVE
627F:00          186 YSAV1      DFB  $00      ; Y-REGISTER SAVE

```

## PROGRAM RM-1, CONT'D . . .

6280: 189 ; \*\*\* POINTER FILE \*\*\*

6280:A0	62	191	PF0	DW	M1.0	; POINTER FILE
6282:B6	62	192	PF1	DW	M1.1	;
6284:FA	63	193	PF2	DW	M1.2	;
6286:05	64	194	PF3	DW	M1.3	;
6288:08	64	195	PF4	DW	M1.4	;
628A:0B	64	196	PF5	DW	M1.5	;
628C:0E	64	197	PF6	DW	M1.6	;
628E:11	64	198	PF7	DW	M1.7	;
6290:14	64	199	PF8	DW	M1.8	;
6292:17	64	200	PF9	DW	M1.9	;
6294:1A	64	201	PF10	DW	M1.10	;
6296:1D	64	202	PF11	DW	M1.11	;
6298:20	64	203	PF12	DW	M1.12	;
629A:23	64	204	PF13	DW	M1.13	;
629C:26	64	205	PF14	DW	M1.14	;
629E:29	64	206	PF15	DW	M1.15	;

62A0: 208 ; \*\*\* MESSAGE FILE \*\*\*

62A0:CD	C5	D3	210	M1.0	ASC	"MESSAGE FILE METHOD"
62A3:D3	C1	C7				
62A6:C5	A0	C6				
62A9:C9	CC	C5				
62AC:A0	CD	C5				
62AF:D4	C8	CF				
62B2:C4						
62B3:8D	8D	00	211		DFB	C,C,X
62B6:D7	C9	D4	213	M1.1	ASC	"WITH THIS METHOD, ALL OF THE MESSAGES"
62B9:C8	A0	D4				
62BC:C8	C9	D3				
62BF:A0	CD	C5				
62C2:D4	C8	CF				
62C5:C4	AC	A0				
62C8:A0	C1	CC				
62CB:CC	A0	CF				
62CE:C6	A0	D4				
62D1:C8	C5	A0				
62D4:CD	C5	D3				
62D7:D3	C1	C7				
62DA:C5	D3	A0				
62DD:8D			214		DFB	C

## PROGRAM RM-1, CONT'D . . .

62DE:C1 D2 C5	217	ASC	"ARE COMBINED INTO A COMMON TEXT FILE
62E1:A0 C3 CF			
62E4:CD C2 C9			
62E7:CE C5 C4			
62EA:A0 C9 CE			
62ED:D4 CF A0			
62F0:C1 A0 C3			
62F3:CF CD CD			
62F6:CF CE A0			
62F9:D4 C5 D8			
62FC:D4 A0 C6			
62FF:C9 CC C5			
6302:AE			
6303:8D 8D	218	DFB	C,C
6305:C1 A0 D0	220	ASC	"A POINTER FILE IS USED TO DECIDE WHICH
6308:CF C9 CE			
630B:D4 C5 D2			
630E:A0 C6 C9			
6311:CC C5 A0			
6314:C9 D3 A0			
6317:D5 D3 C5			
631A:C4 A0 D4			
631D:CF A0 C4			
6320:C5 C3 C9			
6323:C4 C5 A0			
6326:D7 C8 C9			
6329:C3 C8 A0			
632C:8D	221	DFB	C
632D:CD C5 D3	223	ASC	"MESSAGE IS TO BE OUTPUT.
6330:D3 C1 C7			
6333:C5 A0 C9			
6336:D3 A0 D4			
6339:CF A0 C2			
633C:C5 A0 CF			
633F:D5 D4 D0			
6342:D5 D4 AE			
6345:8D 8D	224	DFB	C,C
6347:D5 D3 C5	226	ASC	"USES INCLUDE TEXT DATA BASES AND OTHER
634A:D3 A0 C9			
634D:CE C3 CC			
6350:D5 C4 C5			
6353:A0 D4 C5			
6356:D8 D4 A0			
6359:C4 C1 D4			
635C:C1 A0 C2			
635F:C1 D3 C5			
6362:D3 A0 C1			
6365:CE C4 A0			
6368:CF D4 C8			
636B:C5 D2			
636D:8D	227	DFB	C



## PROGRAM RM-1, CONT'D . . .

636E:D0 CC C1	230	ASC	"PLACES WHERE LOTS OF CHANGING MESSAGE
6371:C3 C5 D3			
6374:A0 D7 C8			
6377:C5 D2 C5			
637A:A0 CC CF			
637D:D4 D3 A0			
6380:CF C6 A0			
6383:C3 C8 C1			
6386:CE C7 C9			
6389:CE C7 A0			
638C:CD C5 D3			
638F:D3 C1 C7			
6392:C5 D3			
6394:8D	231	DFB	C
6395:C1 D2 C5	233	ASC	"ARE TO BE PRINTED OR DISPLAYED.
6398:A0 D4 CF			
639B:A0 C2 C5			
639E:A0 D0 D2			
63A1:C9 CE D4			
63A4:C5 C4 A0			
63A7:CF D2 A0			
63AA:C4 C9 D3			
63AD:D0 CC C1			
63B0:D9 C5 C4			
63B3:AE			
63B4:8D 8D 8D	234	DFB	C,C,C,C
63B7:8D			
63B8:D4 D9 D0	235	ASC	/TYPE "C" FOR CATALOG, OR "E" FOR EXIT
63BB:C5 A0 A2			
63BE:C3 A2 A0			
63C1:C6 CF D2			
63C4:A0 C3 C1			
63C7:D4 C1 CC			
63CA:CF C7 AC			
63CD:A0 CF D2			
63D0:A0 A2 C5			
63D3:A2 A0 C6			
63D6:CF D2 A0			
63D9:C5 D8 C9			
63DC:D4 AE			
63DE:8D 8D 8D	236	DFB	C,C,C,C
63E1:8D			
63E2:A0 A0 A0	237	ASC	" -< >-"
63E5:A0 A0 A0			
63E8:A0 A0 A0			
63EB:A0 A0 A0			
63EE:A0 AD BC			
63F1:A0 BE AD			
63F4:88 88 88	238	DFB	B,B,B,P,B,X
63F7:60 88 00			

## PROGRAM RM-1, CONT'D . . .

63FA:8D 84	241 M1.2	DFB	C,D
63FC:C3 C1 D4	242	ASC	"CATALOG"
63FF:C1 CC CF			
6402:C7			
6403:8D 00	243	DFB	C,X
6405:A0	245 M1.3	ASC	" "
6406:8D 00	246	DFB	C,X
6408:A0	248 M1.4	ASC	" "
6409:8D 00	249	DFB	C,X
640B:A0	251 M1.5	ASC	" "
640C:8D 00	252	DFB	C,X
640F:A0	254 M1.6	ASC	" "
640F:8D 00	255	DFB	C,X
6411:A0	257 M1.7	ASC	" "
6412:8D 00	258	DFB	C,X
6414:A0	260 M1.8	ASC	" "
6415:8D 00	261	DFB	C,X
6417:A0	263 M1.9	ASC	" "
6418:8D 00	264	DFB	C,X
641A:A0	266 M1.10	ASC	" "
641B:8D 00	267	DFB	C,X
641D:A0	269 M1.11	ASC	" "
641E:8D 00	270	DFB	C,X
6420:A0	272 M1.12	ASC	" "
6421:8D 00	273	DFB	C,X
6423:A0	275 M1.13	ASC	" "
6424:8D 00	276	DFB	C,X
6426:A0	278 M1.14	ASC	" "
6427:8D 00	279	DFB	C,X
6429:A0	281 M1.15	ASC	" "
642A:8D 00	282	DFB	C,X

\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS

## IMBEDDED STRING PRINTER

**a powerful and very sneaky  
way of mixing and matching  
text messages**

I guess I've always been attracted to elegant simplicity, particularly when it is combined with sneakiness. The file based text printer of Ripoff Module 1 is a classic and standard old warhorse that's cumbersome, restrictive, and hard to use. It obviously doesn't qualify. What can we do that is better?

Why do we need a text message file at all? Why not, instead, simply *imbed* the text messages *directly into the source code* when and where they are needed? This way, you can have any number of short and fixed messages anywhere in your program, and you can mix and match modules from all over the lot without any worries at all about creating a big master text file and bunches of pointers to work with it.


The usual excuse for not imbedding text into source code is that the 6502 tends to get violently ill when you feed it ASCII text instead of machine language commands. The trick is to find some elegantly simple way to keep the imbedded messages out of the CPU. The way is called the *imbedded text* method.

With the imbedded text method, you simply insert ASCII text or DOS strings into your source code when and as you need them. Immediately before the strings, you do a jump to a very special subroutine that will grab all the ASCII stuff for its own use, and then let

the 6502 pick up the machine language commands that *follow* the message.

Like so . . .

### HOW TO IMBED TEXT INTO SOURCE CODE:



. . . THE IMPRINT SUBROUTINE AUTOMATICALLY OUTPUTS THE TEXT MESSAGE AND THEN "SKIPS OVER" TO THE NEXT LEGAL INSTRUCTION WHEN FINISHED. . .

. . . ONLY ONE IMPRINT SUBROUTINE IS NEEDED TO HANDLE ANY AND ALL FIXED MESSAGES ANYWHERE IN THE ENTIRE SOURCE CODE.

You will need only one imbedded printing subroutine. This can go anywhere in your program. That sub is called IMPRINT. Any and all program modules can use this lone IMPRINT subroutine any time they want to output a fixed text message. While most of these messages will usually be short, there is essentially no limit, except for memory space, as to how long your messages are, how many messages you use, or how you mix and match them

And all this *without* any pointers or master text files.

IMPRINT works by first finding out who called it. It does this by looking into the stack to find the intended subroutine return address. Not only does IMPRINT find the return address, but it *steals* it off the stack and uses that address as a string pointer. It then increments the return address ASCII character by ASCII character, until the message is finished. Finally, IMPRINT forces a subroutine return that goes *beyond* the imbedded text and picks up on the next mainstream machine language command.


What is elegant and sneaky about the whole thing is that IMPRINT is not really a subroutine at all! IMPRINT is a "mainline" code module that "plugs itself" into high level code when and where it is called. It does this by messing with the stack. First, it pulls the return address off the stack, converting itself into mainline code. When finished outputting text, IMPRINT pushes the return-to-the-next-machine-language address onto the stack and then does a quick RTS, which is nothing but a forced jump.

Sounds hairy.

And it is. But the code is very short and simple. It's also very easy to use once you understand it. And, as further elegance, IMPRINT does not hurt any working registers at all.

Here's a flowchart of IMPRINT . . .

**IMPRINT FLOWCHART:**



IMPRINT sits at \$666B right now, but it is easily put any place you want.

As before, to understand a machine language module, find out what variables are stashed where. Two slots on page zero are set aside as a pointer to the character being output. These are called STRP2 and STRP2+1 and are located at \$EB and \$EC. Three absolute slots are used to save the registers, and are called ASAV2, XSAV2, and YSAV2, and appear as a short stash that follows IMPRINT.

An aside or two. A pair of mnemonics involved in a 16-bit word can be spelled out either as STRP2L and STRP2H, or as STRP2 and STRP2+1. The H and L stand for high and low. The standard way is to

use high and low, but you save on code and EQUs by using the arithmetic addition feature of your assembler. Do an EQU on STRP2, and your STRP2+1 rides along free.

By the way, the 2 tag just stands for module 2. This way, you can combine the ripoff modules anyway you like without worrying about duplicate label errors for common names.

Secondly, there are many different ways to temporarily save your accumulator and X- and Y-registers. It is usually a good idea to save all working registers during a subroutine or service module, so you keep any surprises out of the calling code. We have used absolute stores, since they are the safest and surest way of stashing things without memory conflicts. Absolute stores can take more bytes, can be slower, and are a somewhat harder to relocate than other storage methods. Page zero stores are faster, but you tie up precious and possibly conflicting real estate when you try this. The stack is another obvious stash, but its use gets messy fast, particularly on code like IMPRINT that purposely messes with the stack.

The absolute *worst* place to save working registers is in the monitor register saving subroutines IOSAVE and IOREST . . .

<p><b>Don't EVER use the monitor routines IOSAVE and IOREST!</b></p> <p><b>Sooner or later, they are bound to create problems.</b></p>
--

What happens is that some module will use IOSAVE for its register saves and then may JSR to some other module that also tries to use IOSAVE for its own use. The first save gets overwritten by the second, and the final IOREST does a self-destruct, rather than a restore.

Let's see. Where were we? Back to IMPRINT. We first save our registers to the three absolute locations ASAV2, XSAV2, and YSAV2, and stash these at the end of the module.

The subroutine return address in the 6502's stack pointer takes two bytes. The *low address* is the first one you get back. The *high address* is the second byte you get back. That address points to *one less* than where you end up . . .

<b>6502 SUBROUTINE STACK RULES</b>
Two bytes on a stack are used to save a subroutine return address.
The <b>FIRST</b> byte you get back holds the return address <b>POSITION</b> byte.
The <b>SECOND</b> byte you get back holds the return address <b>PAGE</b> byte.
The <b>RTS</b> command returns you to the return address <b>PLUS ONE</b> .

So, we grab the top of the stack and store it as the low address half

at STRP2. Then we grab the top of the stack again, and this time store it as the high address half at STRP2+1.

But, note at this time that this "return" address is pointing to *one less than* our first ASCII character, rather than to a "safe" 6502 return point. Note also that *we are no longer in a subroutine*. Why? Because the calling code pushed two things onto the stack, and the using code pulled two things back off of the stack. We are thus once again back in high level code!

To get our string pointer STRP2 pointing to our first ASCII character, we simply increment the pair in the usual way. Do this by incrementing STRP2, and then, if you get a zero result, take care of the overflow by incrementing STRP2+1. Since we know we will have to increment to get between characters, we'll arrange things so we only need one increment command, at the head of the loop called NXTCHH2.

Your ASCII or DOS text string gets entered into your calling source code, and should end with some marker. We will use the ASCII double zero NULL command here, since it is simplest.

At this time, we grab the character from the string using the indirect indexed loading that lets us reach any point in the 16-bit address space without any page boundary worries. As before, we have forced the Y-register to \$00, to downgrade the indirect indexed command into a "pure" indirect load.

Having gotten the character, we can test it for a double zero. If we get the double zero, we go on to the exit routine at END2. If not, we output the character to COUT or to Fideyfoo, or wherever.

Next, we have included a JSR to an immediate return that we call HOOK2. This has no present use, but it lets you grab IMPRINT for special effects such as character delay, sound, printing in a weird screen direction, or whatever. To use it, just let the subroutine lead you to your special effects module.

After this unused hook, a relative forced branch that fakes an unconditional jump gets us back to NXTCHR2 and completes the loop.

Processing continues one character at a time until we get to the double zero. Then we branch down to the END2 routine.

At this time, the STRP2 pointer is pointing to the double zero of the last character, which is one less than the address of the continuing machine language code in the mainstream. On a subroutine return, the RTS command always goes to one more than the return address. So, *STRP2 equals the correct subroutine return address* when it is pointing to the end-of-text marker.

All that remains is to get back to the mainstream code. We might be tempted to try using the jump indirect instruction, but this one has a deadly bug that will nail you one time out of 128 . . .

**The JMP indirect command has a deadly bug in it that misses page boundary crossings.**

**DON'T USE IT!**

The newer 65C02's have fixed this bug, but they are not yet in wide use at this writing.

We will return to the main code by the exact opposite way we got into IMPRINT. First we shove the high half of the return address minus one, or STRP2+1 onto the stack, and then we shove the low half of the return address minus one, or STRP2, onto the stack. Miraculously, we are now back into a subroutine. To exit, you simply do a RTS.

On the subroutine return, you return to your mainstream code, exactly on the first valid instruction *following* your text message. Very nicely, all the text went out by way of IMPRINT, and the 6502 is ready to continue on the first valid instruction that follows the message.

Note carefully what happened. We go merrily along doing the usual op codes in the usual way. Then we JSR to some very special code that reads and then outputs everything that follows as text. This continues until an end marker. Then, the special code automatically "skips over" the text part, letting you pick back up on the conventional op codes that follow.

At no time does the 6502 see anything but legal op codes. While there is a big "hole" in your source code that holds text, this part of your source code never gets to the CPU. Nifty.

## A Demo

To use IMPRINT, just load it into a known location in your Apple. In any module where you want to output a text message, insert a JSR IMPRINT, followed by the message, followed by a double zero marker. Then pick up your continuing code, just like you normally would.

DEMO2 shows us how it's done. We first initialize to the text mode, clear the screen, do a tab to center a title, and then switch to inverse. Next, our first message is put down by JSRing to IMPRINT, followed by the "Imbedded String Method" title. We then go back to normal text for a few lines, followed by an inverse "JSR," and more normal text. The messages can be combined end on end as shown. This lets you have long messages that will still print neatly on your source code listing. Once again, the assembler enters the character strings with an ASC command, and enters control commands and end markers using DFBs.

Lines 155 and 156 show how to put a prompt into a fancy cue box. You might want to modify this slightly for best IIe results.

As with the file printer, a DOS command is done by starting with a CR and EOT, or [D] followed by a legal DOS instruction. The user can pick an "E" for exit or a "C" for catalog to demonstrate DOS access. Any other key reprints the message, giving a subtle, obvious, and non-obnoxious cue to the user that he is not paying attention.

The imbedded string method is far better than the file based text printer and the previous ripoff module, particularly when lots of fixed and fairly short messages are spread out in a mix-and-match fashion from program module to module.

Elegant simplicity.



**MIND BENDERS**

- Show how the IMPRINT method can be used with changing, calculated, or disk-based text.
- What else can you do with the concept of a JSR, followed by parameters or values needed by that sub, imbedded in mainstream code?
- Are there any advantages to using BRK to call IMPRINT? How would you do this? What are the limitations?
- Show how “new” EDASM’s byte-counting LST pseudo-op can improve this module.
- How can you link an assembler with a word processor so that long text messages can be easily edited and entered into source code?
- Under what circumstances would you NOT want to use IMPRINT?

**PROGRAM RM-2  
IMBEDDED STRING PRINTER**

----- NEXT OBJECT FILE NAME IS IMPRINT

6500:           3           ORG \$6500           ; PUT MODULE #2 AT \$6500

```
6500:           5 ;       *****
6500:           6 ;       *
6500:           7 ;       *           -< IMPRINT MODULE >-       *
6500:           8 ;       *
6500:           9 ;       *           (IMBEDDED STRING PRINTER)       *
6500:           10 ;       *
6500:           11 ;       *           VERSION 1.0 ($6500-$66A1)       *
6500:           12 ;       *
6500:           13 ;       *           6-15-83                       *
6500:           14 ;       * .....*
6500:           15 ;       *
6500:           16 ;       *           COPYRIGHT C 1983 BY           *
6500:           17 ;       *
6500:           18 ;       *           DON LANCASTER AND SYNERGETICS       *
6500:           19 ;       *           BOX 1300, THATCHER AZ., 85552       *
6500:           20 ;       *
6500:           21 ;       *           ALL COMMERCIAL RIGHTS RESERVED       *
6500:           22 ;       *
6500:           23 ;       *****
```

6500:           25 ;               \*\*\* WHAT IT DOES \*\*\*

```
6500:           27 ;       THIS MODULE OUTPUTS TEXT STRINGS OR DOS COMMANDS
6500:           28 ;       TO THE APPLE II'S OUTPUT HOOKS, USING STRINGS
6500:           29 ;       THAT ARE DIRECTLY IMBEDDED IN THE SOURCE CODE.
6500:           30 ;
6500:           31 ;
6500:           32 ;
```

6500:           34 ;               \*\*\* HOW TO USE IT \*\*\*

```
6500:           36 ;       YOUR CALLING CODE SHOULD HAVE A JSR TO IMPRINT.
6500:           37 ;       THIS JSR SHOULD BE IMMEDIATELY FOLLOWED BY AN ASCII
6500:           38 ;       STRING ENDING WITH AN $00 MARKER.
6500:           39 ;
6500:           40 ;
6500:           41 ;
```

## PROGRAM RM-2, CONT'D . . .

```
6500:      44 ;          *** GOTCHAS ***

6500:      46 ;      THIS METHOD IS BEST USED FOR SHORT, UNRELATED MESSAGES
6500:      47 ;      INTERNAL TO YOUR PROGRAM.
6500:      48 ;
6500:      49 ;      MESSAGES CAN BE ANY LENGTH, BUT MORE THAN 40 CHARACTERS
6500:      50 ;      WILL NOT PRINT CLEANLY ON THE ASSEMBLY LISTING.
6500:      51 ;

6500:      53 ;          *** ENHANCEMENTS ***

6500:      55 ;      DOS COMMANDS ARE OUTPUT BY STARTING THE STRING
6500:      56 ;      WITH A CARRIAGE RETURN AND <CTRL> D.
6500:      57 ;
6500:      58 ;      TO GO DIRECTLY TO THE SCREEN, USE COUT1 RATHER THAN COUT.
6500:      59 ;      THIS IS FASTER, BUT CANNOT CONTROL DOS OR BE PRINTED.
6500:      60 ;

6500:      62 ;          *** RANDOM COMMENTS ***

6500:      64 ;      TO RUN THE DEMO, USE $6500G OR CALL 25856.
6500:      65 ;
6500:      66 ;
6500:      67 ;
6500:      68 ;
6500:      69 ;
```

## PROGRAM RM-2, CONT'D . . .

```
6500:          72 ;          *** HOOKS ***

FDED:          74 COUT      EQU  $FDED      ; OUTPUT CHARACTER VIA HOOKS
FC58:          75 HOME      EQU  $FC58      ; CLEAR SCREEN
C010:          76 KBDSTR    EQU  $C010      ; KEYBOARD RESET
FB2F:          77 INIT      EQU  $FB2F      ; INITIALIZE TEXT SCREEN
FD1B:          78 KEYIN     EQU  $FD1B      ; READ KEYBOARD
F94A:          79 PRBL2     EQU  $F94A      ; PRINT X BLANKS
FE80:          80 SETINV    EQU  $FE80      ; SET INVERSE SCREEN
FE84:          81 SETNORM   EQU  $FE84      ; SET NORMAL SCREEN
FCA8:          82 WAIT      EQU  $FCA8      ; TIME DELAY SET BY ACCUMULATOR

00EB:          84 STRP2     EQU  $EB         ; POINTER TO ASCII STRING

6500:          86 ;          *** TEXTFILE COMMANDS ***

0088:          88 B         EQU  $88        ; BACKSPACE
008D:          89 C         EQU  $8D        ; CARRIAGE RETURN
0084:          90 D         EQU  $84        ; DOS ATTENTION
008A:          91 L         EQU  $8A        ; LINEFEED
0060:          92 P         EQU  $60        ; FLASHING PROMPT
0000:          93 X         EQU  $00        ; END OF MESSAGE
```

## PROGRAM RM-2, CONT'D . . .

```

6500:          96 ;          *** DEMO ***
6500:          97 ;
6500:          98 ;

6500:          100 ;        THE DEMO USES THE IMPRINT MODULE TO OUTPUT
6500:          101 ;        SCREEN MESSAGES AND A DOS CATALOG COMMAND.
6500:          102 ;
6500:          103 ;
6500:          104 ;
6500:          105 ;

6500:20 2F FB 107 DEMO2 JSR INIT      ; GO TO TEXT MODE
6503:20 58 FC 108 JSR HOME      ; CLEAR SCREEN
6506:A2 07 109 LDX #07      ; ADD BLANKS TO START
6508:20 4A F9 110 JSR PRBL2      ;
650B:20 80 FE 111 JSR SETINV     ; INVERSE HEADER
650E:20 6B 66 112 JSR IMPRINT    ; PUT DOWN HEADER

6511:8A 8A 8A 114 DFB          L,L,L
6514:C9 CD C2 115 ASC          "IMBEDDED STRING METHOD"
6517:C5 C4 C4
651A:C5 C4 A0
651D:D3 D4 D2
6520:C9 CE C7
6523:A0 CD C5
6526:D4 C8 CF
6529:C4
652A:8D 8D 00 116 DFB          C,C,X

652D:20 84 FE 118 JSR SETNORM   ; NORMAL TEXT
6530:20 6B 66 119 JSR IMPRINT    ; TOP TEXT LINE

6533:D7 C9 D4 121 ASC          "WITH THIS METHOD, EACH MESSAGE STRING
6536:C8 A0 D4
6539:C8 C9 D3
653C:A0 CD C5
653F:D4 C8 CF
6542:C4 AC A0
6545:C5 C1 C3
6548:C8 A0 CD
654B:C5 D3 D3
654E:C1 C7 C5
6551:A0 D3 D4
6554:D2 C9 CE
6557:C7 A0
6559:8D          122 DFB          C

```

## PROGRAM RM-2, CONT'D . . .

655A:C6 CF CC	125	ASC	"FOLLOWS ITS OWN
655D:CC CF D7			
6560:D3 A0 C9			
6563:D4 D3 A0			
6566:CF D7 CE			
6569:A0			
656A:00	126	DFB	X
656B:20 80 FE	128	JSR SETINV	; INVERSE TEXT
656E:20 6B 66	129	JSR IMPRINT	;
6571:CA D3 D2	131	ASC	"JSR"
6574:00	132	DFB	X
6575:20 84 FE	134	JSR SETNORM	; RETURN TO NORMAL TEXT
6578:20 6B 66	135	JSR IMPRINT	; AFTER JSR
657B:A0 C3 C1	137	ASC	" CALL, IMBEDDED IN
657E:CC CC AC			
6581:A0 C9 CD			
6584:C2 C5 C4			
6587:C4 C5 C4			
658A:A0 C9 CE			
658D:8D	138	DFB	C
658E:C9 D4 D3	140	ASC	"ITS OWN SOURCE CODE. "
6591:A0 CF D7			
6594:CE A0 D3			
6597:CF D5 D2			
659A:C3 C5 A0			
659D:C3 CF C4			
65A0:C5 AE A0			
65A3:A0			
65A4:CE CF A0	142	ASC	"NO POINTERS AND
65A7:D0 CF C9			
65AA:CE D4 C5			
65AD:D2 D3 A0			
65B0:C1 CE C4			
65B3:8D	143	DFB	C
65B4:CE CF A0	145	ASC	"NO MASTER FILE ARE NEEDED.
65B7:CD C1 D3			
65BA:D4 C5 D2			
65BD:A0 C6 C9			
65C0:CC C5 A0			
65C3:C1 D2 C5			
65C6:A0 CE C5			
65C9:C5 C4 C5			
65CC:C4 AE			
65CE:8D 8D	146	DFB	C,C

PROGRAM RM-2, CONT'D . . .

65D0:C2 C5 D3	149	ASC	"BEST USE IS FOR FIXED, SHORT MESSAGES.
65D3:D4 A0 D5			
65D6:D3 C5 A0			
65D9:C9 D3 A0			
65DC:C6 CF D2			
65DF:A0 C6 C9			
65E2:D8 C5 C4			
65E5:AC A0 D3			
65E8:C8 CF D2			
65EB:D4 A0 CD			
65EE:C5 D3 D3			
65F1:C1 C7 C5			
65F4:D3 AE			
65F6:8D 8D	150	DFB	C,C
65F8:D4 D9 D0	152	ASC	/TYPE "C" FOR CATALOG, OR "E" FOR EXIT.
65FB:C5 A0 A2			
65FE:C3 A2 A0			
6601:C6 CF D2			
6604:A0 C3 C1			
6607:D4 C1 CC			
660A:CF C7 AC			
660D:A0 CF D2			
6610:A0 A2 C5			
6613:A2 A0 C6			
6616:CF D2 A0			
6619:C5 D8 C9			
661C:D4 AE			
661E:8D 8D	153	DFB	C,C
6620:A0 A0 A0	155	ASC	" -< >-"
6623:A0 A0 A0			
6626:A0 A0 A0			
6629:A0 A0 A0			
662C:A0 A0 AD			
662F:BC A0 BE			
6632:AD			
6633:88 88 88	156	DFB	B,B,B,P,B,X
6636:60 88 00			

## PROGRAM RM-2, CONT'D . . .

```
6639:2C 10 C0 159 AGAIN2 BIT KBDSTR ; RESET KEY STROBE
663C:20 1B FD 160 KBD2 JSR KEYIN ; READ KEYBOARD
663F:C9 C5 161 CMP #C5 ; AN "E" FOR EXIT?
6641:F0 21 162 BEQ EXIT2 ; YES, EXIT
6643:C9 C3 163 CMP #C3 ; A "C" FOR CATALOG?
6645:D0 1A 164 BNE RETRY2 ; NO, REPRINT SCREEN

6647:20 58 FC 166 JSR HOME ; CLEAR SCREEN FOR CATALOG
664A:20 6B 66 167 JSR IMPRINT ;

664D:8D 84 169 DFB C,D ; DOS HEADER
664F:C3 C1 D4 170 ASC "CATALOG" ;
6652:C1 CC CF
6655:C7
6656:8D 00 171 DFB C,X ; DOS TRAILER

6658:20 6B 66 173 JSR IMPRINT ; PROMPT AFTER CATALOG
665B:8D 60 00 174 DFB C,P,X

665E:18 176 CLC ; BRANCH ALWAYS
665F:90 D8 177 BCC AGAIN2 ;
6661:4C 00 65 178 RETRY2 JMP DEMO2 ; TOO FAR FOR BRANCH
6664:20 58 FC 179 EXIT2 JSR HOME ; CLEAR SCREEN
6667:2C 10 C0 180 BIT KBDSTR ; RESET KEYSTROBE
666A:60 181 RTS ; AND RETURN
```



## PROGRAM RM-2, CONT'D . . .

```

666B:      184 ;          *** IMPRINT MODULE ***
666B:      185 ;
666B:      186 ;

666B:      188 ;          THIS MODULE UNPOPS THE STACK TO FIND THE
666B:      189 ;          IMBEDDED STRING. IT OUTPUTS ONE CHARACTER
666B:      190 ;          AT A TIME TILL A $00 MARKER IS FOUND. THEN
666B:      191 ;          IT JUMPS BACK TO THE CALLING PROGRAM JUST
666B:      192 ;          BEYOND THE STRING.
666B:      193 ;

666B:8E A0 66 195 IMPRINT STX XSAV2      ; SAVE REGISTERS
666E:8C A1 66 196          STY YSAV2      ;
6671:8D 9F 66 197          STA ASAV2      ;

6674:68          199          PLA          ; GET POINTER LOW AND SAVE
6675:85 EB      200          STA STRP2      ;
6677:68          201          PLA          ; GET POINTER HIGH AND SAVE
6678:85 EC      202          STA STRP2+1    ;

667A:A0 00      204          LDY #$00      ; NO INDEXING
667C:E6 EB      205 NXTCHR2 INC STRP2      ; GET NEXT HIGH ADDRESS
667E:D0 02      206          BNE NOC2      ; SKIP IF NO CARRY
6680:E6 EC      207          INC STRP2+1    ; INCREMENT HIGH ADDRESS
6682:B1 EB      208 NOC2     LDA (STRP2),Y ; GET CHARACTER
6684:F0 09      209          BEQ END2      ; IF ZERO MARKER
6686:20 9E 66   210          JSR HOOK2     ; FOR SPECIAL EFFECTS
6689:20 ED FD   211          JSR COUT     ; PRINT CHARACTER
668C:18          212          CLC          ; BRANCH ALWAYS
668D:90 ED      213          BCC NXTCHR2   ;

668F:A5 EC      215 END2     LDA STRP2+1  ; RESTORE PC LOW
6691:48          216          PHA          ;
6692:A5 EB      217          LDA STRP2      ; RESTORE PC HIGH
6694:48          218          PHA          ;
6695:AE A0 66   219          LDX XSAV2      ;
6698:AC A1 66   220          LDY YSAV2      ; RESTORE REGISTERS
669B:AD 9F 66   221          LDA ASAV2      ;
669E:60          222 HOOK2   RTS          ; AND EXIT

669F:      224 ;          *** STASH ***

669F:00      226 ASAV2     DFB $00          ; ACCUMULATOR SAVE
66A0:00      227 XSAV2     DFB $00          ; X-REGISTER SAVE
66A1:00      228 YSAV2     DFB $00          ; Y-REGISTER SAVE

```

\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS

## MONITOR TIME DELAY

### how to use a monitor subroutine for sounds, animation, and other timing

If everyone is always worried about getting their programs to run fast enough, why on earth would you ever *purposefully* want to stall for time?

Because, of course, some of the most useful and most interesting Apple uses center on carefully controlled sequences of time delays. The most obvious applications are in sound and music, where you wait for a while, and then change the position of a speaker cone. How long you wait sets the *pitch* of the tone, while the number of times you change the cone sets the *duration* of the note. Much more on this in the next two ripoff modules.

Another place where you purposely want to delay precise amounts of time involves baud-rate generation. Most often, though, these repeated time delays are done outside your CPU with a special serial transmitter chip. But other times, your CPU can be asked to generate a special frequency or a timing waveform that involves carefully controlled delays.

Producing the 40-kHz ultrasonic control signal for a BSR remote power controller is one use. Here a few bytes of software can replace bunches of specialized and unneeded hardware. Many industrial uses of Apples involve function and signal generators of one sort or another.

The real biggie of the time delay world centers on animation. To animate something, you put a pattern on the screen, wait a while, and then replace or modify that pattern into something different. Done just right, the changing patterns will give you the illusion of continuous motion. One very new use of Apple timing lets you carefully lock your animation to your video displays. This offers you everything from flawless and glitchless animation to mixing and matching of text, HIRES, and LORES together all at once.

Finally, there are the long term uses of time delay. Things that control appliances, turn on sprinklers, or that keep hourly, daily, weekly, or even monthly tabs on whatever it is that needs its tabs kept.

As with any programming technique, there are several different popular ways you can go about stalling for time. Which one you use depends on what you are trying to accomplish and how much else has to happen while the time delay is taking place.

The fundamental unit of Apple time delay is called a *clock cycle*. One clock cycle is roughly one microsecond, so you will need around one million of these for a one second delay. The Apple clock cycles are crystal controlled, so they are themselves accurate to at least one part in a million.

But there is one possible source of inaccuracy that will get to you if you aren't careful. Apple clock cycles are *not* precisely one microsecond long . . .

**An Apple clock cycle is ROUGHLY 1 microsecond long.**

**An Apple clock cycle takes EXACTLY 0.978 microseconds or 978 nanoseconds.**

**A microsecond takes up EXACTLY 1.023 Apple clock cycles.**

Just to confuse you further, these times are *average* values. Each 65th clock cycle is one-seventh longer than all the rest. This is done to uniquely solve a sticky timing glitch. The result is a tiny, and usually negligible, jitter in outside-world timing applications.

For most everyday needs, you simply say a cycle is a microsecond, and live with the two percent error you get. But, if you need an exact number of Apple clock cycles, or an exactly specified time delay, you have to "fine tune" your thinking to get precisely what you need.

As examples, locking to an Apple field takes a precise delay of 17030 Apple clock cycles, no more and no less. The time does not matter here; the cycles are everything. If you must have precisely one second of delay, you should use 1,022,727 clock cycles and not an even million. But never make things bunches more precise than you really need, since extra accuracy is often a pointless waste of time and effort.

I guess I really get into time delay techniques whole hog, since some of the most mind-blowing and most challenging Apple uses involve carefully controlled time delays where an exact result has to be gotten in an exact number of cycles. This, of course, is what most of the cheap video stuff was all about, (Sams 21524 and 21723) and is an ongoing challenge in the Enhance series (Sams 21822, etc.).

Sometimes you will only want to delay for a few clock cycles. Other times you might need great heaping bunches of cycles. So, you have a choice of time delay methods. Here, going from short to long, are some possible . . .

WAYS TO STALL FOR TIME
cycle burner uppers simple loop monitor delay  triple monitor delay combined use offloading

Burning up clock cycles is one good way for short time delays of a few microseconds. What you do is throw in some Apple CPU commands that don't really do anything but burn up clock cycles. These might be used to equalize two paths through time critical code, to provide video positioning, or be used anywhere else you need only a few cycles of correction.

Here are some standard . . .

CYCLE BURNER UPPERS
2 cycles . . . NOP
3 cycles . . . BCC taken or JMP
4 cycles . . . NOP and NOP
5 cycles . . . NOP and BCC taken
6 cycles . . . NOP and NOP and NOP
7 cycles . . . PHA and PLA

The object of the game is to use as few code bytes as possible for your delay and to not hurt anything else in the way of flags or working registers. You can find the "efficiency" of a 6502 instruction by dividing the number of cycles delayed by the number of bytes needed. NOPs are often your safest bet since they do the least damage.

Doing one single cycle of delay gets tricky. While many of the "illegal" commands in the 65C02 default to single cycle NOPs, there is no obvious way to do a single cycle delay with the older and stock 6502's. The way I usually handle a single delay cycle is to set up the *difference* between two paths that have even and odd total clock cycles. For instance, if your carry flag is set, a BCC takes up two cycles and a BCS takes up three.

If you do use branches for exact time delays, watch your page boundary crossings! A mysterious "extra" clock cycle or two will sometimes result if your code crosses a page when you didn't expect it to.

Once you get good at it, you should try to build your time delays into code commands, so that your code does other good stuff at the same time it is providing your time delay.

Needless to say, cycle burner uppers get old for more than a few clock cycles worth of delay. There are obviously better ways to stall for a second than by using 511,350 NOPs in a row.

What usually happens for longer delays is that you try to take up most of the delay with some efficient code, and then, if you have to, "equalize" with cycle burner uppers to hit any magic values you need.

The next larger arrow in our delay quiver is the simple loop. Like so . . .

```
                LDX #$06
LOOP            DEX
                BNE LOOP
```

What you have done is filled a loop with a value and then counted it down. Go through the math, and you will find you get a total of  $5N+1$  clock cycles.  $N$  here is the hex value you initially load the loop with. So this dude is good for 6, 11, 16, 21, 26, . . . clock cycles.

Note that a loop value of zero will go all the way around, rather than falling through, for a total of 1281 clock cycles. In terms of audio frequencies, this equals a square wave's half-period of just under 400 Hz. The reason the zero is missed is that it immediately is decremented to  $\$FF$  and thus gets "caught" by the taken BNE branch. Zero is thus the *maximum* possible loop time.

For longer delays, you can put extra cycle burner uppers inside the loop, or else go to a loop within a loop. As examples, a NOP inside your loop changes the formula to  $7N+1$  cycles, while two simple loops inside each other will get you over a tenth of a second of delay.

But there is a much better way for medium-length delays. There is a super elegant and super versatile time delay built into the Apple monitor that is most useful for longer time delays. To use this routine, all you do is put a magic value into the accumulator and call the routine. Like this . . .

<b>USING THE MONITOR TIME DELAY</b>
1. Put a magic value in A. 2. Do a JSR to $\$FCA8$ .



And that's all there is to it. Go through the code on this, and you'll find it to be disgustingly elegant. All that gets used is the accumulator and two "borrowed" stack locations. Nothing else is tied up or used at all.

Part of the elegance involves the timing range you get. You can go anywhere from 13 clock cycles, on up to a sixth of a second, starting with only a single 8-bit magic value. Very conveniently, the available 256 time-delay values are spread out in a somewhat "log" fashion, so you get "tight" spacing on small delays and "wide" spacing on long delays.

The only reason this routine is not used as much as it should be is that the formula for the "magic" delay value is scary. Spooky even. And so misunderstood that even Apple has misprinted its formula in several different places.

The magic formula, expressed in *clock cycles* is . . .

$$\text{MONITOR DELAY CYCLES} = 13 + 13.5 * A + 2.5 * A * A$$

If you want the time delay in microseconds, just multiply the above result by 0.978.

Apple failed to do this on page 63 of the *Apple II Reference Manual* and on page 223 of the *Apple IIe Reference Manual*. To correct your manual, cross out "microseconds" and write in "clock cycles!"

For milliseconds, divide the scaled result by 1000, and for seconds of delay, divide by a million. As usual, don't forget to convert your decimal values into hex before assembling them, or your delay will end up wrong just about every time.

Since that formula is so ugly and nasty that it might even scare an eighth grader, we'll just spell it all out for you in longhand . . .

TIME DELAY VALUES FOR THE MONITOR WAIT SUBROUTINE				
HEX A	DECIMAL A	CYCLES	MICROSECONDS	MILLISECONDS
\$00	0	13	12	.012
\$01	1	29	28	.028
\$02	2	50	48	.048
\$03	3	76	74	.074
\$04	4	107	104	.104
\$05	5	143	139	.139
\$06	6	184	179	.179
\$07	7	230	224	.224
\$08	8	281	274	.274
\$09	9	337	329	.329
\$0A	10	398	389	.389
\$0B	11	464	453	.453
\$0C	12	535	522	.522
\$0D	13	611	597	.597
\$0E	14	692	676	.676
\$0F	15	778	760	.76
\$10	16	869	849	.849
\$11	17	965	943	.943
\$12	18	1066	1042	1.042
\$13	19	1172	1145	1.145
\$14	20	1283	1254	1.254
\$15	21	1399	1367	1.367
\$16	22	1520	1485	1.485
\$17	23	1646	1608	1.608
\$18	24	1777	1737	1.737
\$19	25	1913	1869	1.869
\$1A	26	2054	2007	2.007
\$1B	27	2200	2150	2.15
\$1C	28	2351	2298	2.298
\$1D	29	2507	2450	2.45
\$1E	30	2668	2608	2.608
\$1F	31	2834	2770	2.77

## TIME DELAY TABLE, CONTINUED

HEX A	DECIMAL A	CYCLES	MICROSECONDS	MILLISECONDS
\$20	32	3005	2937	2.937
\$21	33	3181	3109	3.109
\$22	34	3362	3286	3.286
\$23	35	3548	3468	3.468
\$24	36	3739	3654	3.654
\$25	37	3935	3846	3.846
\$26	38	4136	4043	4.043
\$27	39	4342	4244	4.244
\$28	40	4553	4450	4.45
\$29	41	4769	4661	4.661
\$2A	42	4990	4877	4.877
\$2B	43	5216	5098	5.098
\$2C	44	5447	5324	5.324
\$2D	45	5683	5555	5.555
\$2E	46	5924	5790	5.79
\$2F	47	6170	6031	6.031
\$30	48	6421	6276	6.276
\$31	49	6677	6526	6.526
\$32	50	6938	6782	6.782
\$33	51	7204	7042	7.042
\$34	52	7475	7306	7.306
\$35	53	7751	7576	7.576
\$36	54	8032	7851	7.851
\$37	55	8318	8130	8.13
\$38	56	8609	8415	8.415
\$39	57	8905	8704	8.704
\$3A	58	9206	8999	8.999
\$3B	59	9512	9298	9.298
\$3C	60	9823	9602	9.602
\$3D	61	10139	9911	9.911
\$3E	62	10460	10224	10.224
\$3F	63	10786	10543	10.543
\$40	64	11117	10867	10.867
\$41	65	11453	11195	11.195
\$42	66	11794	11528	11.528
\$43	67	12140	11867	11.867
\$44	68	12491	12210	12.21
\$45	69	12847	12558	12.558
\$46	70	13208	12911	12.911
\$47	71	13574	13268	13.268
\$48	72	13945	13631	13.631
\$49	73	14321	13999	13.999
\$4A	74	14702	14371	14.371
\$4B	75	15088	14748	14.748
\$4C	76	15479	15130	15.13
\$4D	77	15875	15518	15.518
\$4E	78	16276	15910	15.91
\$4F	79	16682	16306	16.306

## TIME DELAY TABLE, CONTINUED

HEX A	DECIMAL A	CYCLES	MICROSECONDS	MILLISECONDS
\$50	80	17093	16708	16.708
\$51	81	17509	17115	17.115
\$52	82	17930	17526	17.526
\$53	83	18356	17943	17.943
\$54	84	18787	18364	18.364
\$55	85	19223	18790	18.79
\$56	86	19664	19221	19.221
\$57	87	20110	19657	19.657
\$58	88	20561	20098	20.098
\$59	89	21017	20544	20.544
\$5A	90	21478	20995	20.995
\$5B	91	21944	21450	21.45
\$5C	92	22415	21911	21.911
\$5D	93	22891	22376	22.376
\$5E	94	23372	22846	22.846
\$5F	95	23858	23321	23.321
\$60	96	24349	23801	23.801
\$61	97	24845	24286	24.286
\$62	98	25346	24776	24.776
\$63	99	25852	25270	25.27
\$64	100	26363	25770	25.77
\$65	101	26879	26274	26.274
\$66	102	27400	26783	26.783
\$67	103	27926	27298	27.298
\$68	104	28457	27817	27.817
\$69	105	28993	28341	28.341
\$6A	106	29534	28869	28.869
\$6B	107	30080	29403	29.403
\$6C	108	30631	29942	29.942
\$6D	109	31187	30485	30.485
\$6E	110	31748	31034	31.034
\$6F	111	32314	31587	31.587
\$70	112	32885	32145	32.145
\$71	113	33461	32708	32.708
\$72	114	34042	33276	33.276
\$73	115	34628	33849	33.849
\$74	116	35219	34427	34.427
\$75	117	35815	35009	35.009
\$76	118	36416	35597	35.597
\$77	119	37022	36189	36.189
\$78	120	37633	36786	36.786
\$79	121	38249	37389	37.389
\$7A	122	38870	37996	37.996
\$7B	123	39496	38608	38.608
\$7C	124	40127	39224	39.224
\$7D	125	40763	39846	39.846
\$7E	126	41404	40473	40.473
\$7F	127	42050	41104	41.104



## TIME DELAY TABLE, CONTINUED

HEX A	DECIMAL A	CYCLES	MICROSECONDS	MILLISECONDS
\$80	128	42701	41740	41.74
\$81	129	43357	42382	42.382
\$82	130	44018	43028	43.028
\$83	131	44684	43679	43.679
\$84	132	45355	44335	44.335
\$85	133	46031	44996	44.996
\$86	134	46712	45661	45.661
\$87	135	47398	46332	46.332
\$88	136	48089	47007	47.007
\$89	137	48785	47688	47.688
\$8A	138	49486	48373	48.373
\$8B	139	50192	49063	49.063
\$8C	140	50903	49758	49.758
\$8D	141	51619	50458	50.458
\$8E	142	52340	51163	51.163
\$8F	143	53066	51872	51.872
\$90	144	53797	52587	52.587
\$91	145	54533	53306	53.306
\$92	146	55274	54031	54.031
\$93	147	56020	54760	54.76
\$94	148	56771	55494	55.494
\$95	149	57527	56233	56.233
\$96	150	58288	56977	56.977
\$97	151	59054	57726	57.726
\$98	152	59825	58479	58.479
\$99	153	60601	59238	59.238
\$9A	154	61382	60001	60.001
\$9B	155	62168	60770	60.77
\$9C	156	62959	61543	61.543
\$9D	157	63755	62321	62.321
\$9E	158	64556	63104	63.104
\$9F	159	65362	63892	63.892
\$A0	160	66173	64685	64.685
\$A1	161	66989	65482	65.482
\$A2	162	67810	66285	66.285
\$A3	163	68636	67092	67.092
\$A4	164	69467	67905	67.905
\$A5	165	70303	68722	68.722
\$A6	166	71144	69544	69.544
\$A7	167	71990	70371	70.371
\$A8	168	72841	71203	71.203
\$A9	169	73697	72040	72.04
\$AA	170	74558	72881	72.881
\$AB	171	75424	73728	73.728
\$AC	172	76295	74579	74.579
\$AD	173	77171	75435	75.435
\$AE	174	78052	76297	76.297
\$AF	175	78938	77163	77.163

## TIME DELAY TABLE, CONTINUED

HEX A	DECIMAL A	CYCLES	MICROSECONDS	MILLISECONDS
\$B0	176	79829	78034	78.034
\$B1	177	80725	78910	78.91
\$B2	178	81626	79790	79.79
\$B3	179	82532	80676	80.676
\$B4	180	83443	81566	81.566
\$B5	181	84359	82462	82.462
\$B6	182	85280	83362	83.362
\$B7	183	86206	84267	84.267
\$B8	184	87137	85177	85.177
\$B9	185	88073	86092	86.092
\$BA	186	89014	87012	87.012
\$BB	187	89960	87937	87.937
\$BC	188	90911	88867	88.867
\$BD	189	91867	89801	89.801
\$BE	190	92828	90740	90.74
\$BF	191	93794	91685	91.685
\$C0	192	94765	92634	92.634
\$C1	193	95741	93588	93.588
\$C2	194	96722	94547	94.547
\$C3	195	97708	95511	95.511
\$C4	196	98699	96479	96.479
\$C5	197	99695	97453	97.453
\$C6	198	100696	98432	98.432
\$C7	199	101702	99415	99.415
\$C8	200	102713	100403	100.403
\$C9	201	103729	101396	101.396
\$CA	202	104750	102394	102.394
\$CB	203	105776	103397	103.397
\$CC	204	106807	104405	104.405
\$CD	205	107843	105418	105.418
\$CE	206	108884	106435	106.435
\$CF	207	109930	107458	107.458
\$D0	208	110981	108485	108.485
\$D1	209	112037	109518	109.518
\$D2	210	113098	110555	110.555
\$D3	211	114164	111597	111.597
\$D4	212	115235	112644	112.644
\$D5	213	116311	113695	113.695
\$D6	214	117392	114752	114.752
\$D7	215	118478	115814	115.814
\$D8	216	119569	116880	116.88
\$D9	217	120665	117952	117.952
\$DA	218	121766	119028	119.028
\$DB	219	122872	120109	120.109
\$DC	220	123983	121195	121.195
\$DD	221	125099	122286	122.286
\$DE	222	126220	123382	123.382
\$DF	223	127346	124482	124.482

## TIME DELAY TABLE, CONTINUED

HEX A	DECIMAL A	CYCLES	MICROSECONDS	MILLISECONDS
\$E0	224	128477	125588	125.588
\$E1	225	129613	126698	126.698
\$E2	226	130754	127814	127.814
\$E3	227	131900	128934	128.934
\$E4	228	133051	130059	130.059
\$E5	229	134207	131189	131.189
\$E6	230	135368	132324	132.324
\$E7	231	136534	133464	133.464
\$E8	232	137705	134608	134.608
\$E9	233	138881	135758	135.758
\$EA	234	140062	136913	136.913
\$EB	235	141248	138072	138.072
\$EC	236	142439	139236	139.236
\$ED	237	143635	140405	140.405
\$EE	238	144836	141579	141.579
\$EF	239	146042	142758	142.758
\$F0	240	147253	143942	143.942
\$F1	241	148469	145130	145.13
\$F2	242	149690	146324	146.324
\$F3	243	150916	147522	147.522
\$F4	244	152147	148726	148.726
\$F5	245	153383	149934	149.934
\$F6	246	154624	151147	151.147
\$F7	247	155870	152365	152.365
\$F8	248	157121	153588	153.588
\$F9	249	158377	154816	154.816
\$FA	250	159638	156048	156.048
\$FB	251	160904	157286	157.286
\$FC	252	162175	158528	158.528
\$FD	253	163451	159776	159.776
\$FE	254	164732	161028	161.028
\$FF	255	166018	162285	162.285

A copy of this listing appears on the companion diskette as a bonus program. Make as many copies as you like in any format you care to.

We'll find out just how to use the monitor delay subroutine shortly. Note that you do not get every value in the range you need. What you do is take the nearest value and then either live with it or else "pad" it with cycle burner uppers.

Let's quickly round out our survey of ways to stall for time. If you use the monitor delay three times in a row with just the right *different* "magic" values, you can hit practically any exact value over a one to three hundred millisecond range. This was needed and used extensively in *Enhancing Your Apple II* (Sams 21822).

As another bonus program on the support diskette for this book, we'll throw in an automatic magic number finder that quickly solves the triple delay problem for you. The task is not trivial. More details on this support diskette are found inside the back cover.

On longer delays, it is always best to try and do other things while you are stalling for time. For instance, you can increment a random number pair while you are waiting for someone to press a key. Or you can use your animated graphics plotting time as part of the time delay for a sound. Always suspect long times spent "wheel spinning," and see if you can't replace stalling code with some useful yet time consuming task instead . . .

**Avoid "wheel spinning" for wheel spinning's sake.  
ALWAYS try and make your time delay code handle other useful tasks.**

The "best" way to stall for time is to have something other than the CPU do the delaying for you. This frees up your Apple to go on to do other useful things. For instance, you can send a single and fast "transmit" command to a serial card whose separate UART takes its good old time outputting a serial code. Or, send your music commands to a music chip. Or your timer commands to a timer chip. Or use a real time clock chip to interrupt your Apple for those things that take really long time delays, such as control of a sprinkler system.

Unfortunately, all of these "offloaders" take special hardware and add to your system cost. They also limit who you can sell your product to. Sometimes it is best to do your initial timing with the CPU and then later offload cumbersome timing once your product is better defined.

### Using the Monitor Delay

Let's find out how to use the monitor delay for some exciting and noisy animation. So stunning, in fact, that it might earn a fifth grader a B— if his teacher was feeling generous. While we are at it, we will pick up some fundamentals of LORES plotting using the existing monitor LORES subs.

Many people look down on LORES, but a thorough understanding of LORES graphics is almost essential if you are ever going to handle HIRES. The IIe now offers double LORES graphics of 24 X 80 color blocks, which considerably eases the "chunkiness" of the display.

LORES animation and repeated mapping can be done much faster and with far fewer bytes than can be done in HIRES. And, thanks to the exact field sync of the Enhancing series, you can easily mix and match text, LORES, and HIRES together anyplace you want on the screen all at the same time.

Our main program is called DEMO3. DEMO3 consists of three subroutines, just as any "high level" code should be made up entirely of subroutine calls. The first subroutine clears the screen and draws an empty bucket on the screen. The second subroutine fills the bucket at a one layer per second rate. The third subroutine causes an explosion when the bucket is completely filled. Calling the fire department or pressing any key ends the explosion.

We will let you do your own flowchart on this, since nothing sneaky is involved.

The first subroutine is called DRAWCUP. This one initializes the LORES screen and clears it using the existing SETGR and CLRSCR monitor subs. You then set the bucket color to green using the SETCOL subroutine, and then draw your bucket.

Bucket drawing is done using the HLINE and VLINE monitor subroutines. You enter HLINE with the vertical position in the accumulator, the left end line position in the Y register, and the right end line position in page zero location \$2C.

Alike but different somehow, you enter VLINE with the horizontal position in the Y register, the top-most line position in the accumulator, and the bottom-most line position in page zero location \$2D.

Note how the use of labels HEND for \$2C and VBOT for \$2D eases remembering these values.

The FILLCUP subroutine fills the cup one level at a time, spending one second per level. Several sub-subs are involved. The TENTHS subroutine uses the monitor delay to produce one-tenth of a second delay. In this demo, we won't worry about exact timing values, since they are not at all critical.

Since we cannot do a one-second delay directly with the monitor sub, we instead use our own SECONDS subroutine, which calls the TENTHS subroutine ten times in a row to get a one-second delay.

To round out our time delays, there is also a TENMSEC subroutine that generates a 10-millisecond delay, useful to produce a sound effect as part of the BRACK subroutine. More details on sound effects appear in the next two ripoff modules.

The "explosion" is done by rapidly changing the screen modes while whapping the speaker. It sounds and looks awful.

**MIND BENDERS**

- Why does the liquid stay inside the cup, rather than overflowing the existing cup sides?
- What are the exact time delays in use, including all sub timing and all overhead code?
- Improve the animation and the display so it would earn a seventh grader an A-.
- Only certain cup and liquid colors are compatible on an average color set. Why? Which combinations look best in both color and black and white?
- Redo this demo in HIRES. Do an on-screen splash. Then include a *real* squirt gun in your demo.

PROGRAM RM-3  
MONITOR TIME DELAY

----- NEXT OBJECT FILE NAME IS TIME DELAY

6700: 3           ORG \$6700       ; PUT MODULE #3 AT \$6700

```
6700: 5 ; *****
6700: 6 ; *
6700: 7 ; *           -< TIME DELAY >-           *
6700: 8 ; *
6700: 9 ; *           (USING MONITOR WAIT)           *
6700: 10 ; *
6700: 11 ; *           VERSION 1.0 ($6700-$67AC)           *
6700: 12 ; *
6700: 13 ; *           11-24-82           *
6700: 14 ; * .....*
6700: 15 ; *
6700: 16 ; *           COPYRIGHT C 1982 BY           *
6700: 17 ; *
6700: 18 ; *           DON LANCASTER AND SYNERGETICS           *
6700: 19 ; *           BOX 1300, THATCHER AZ., 85552           *
6700: 20 ; *
6700: 21 ; *           ALL COMMERCIAL RIGHTS RESERVED           *
6700: 22 ; *
6700: 23 ; *****
```

6700: 25 ;           \*\*\* WHAT IT DOES \*\*\*

```
6700: 27 ; THIS PROGRAM SHOWS HOW TO USE THE MONITOR WAIT
6700: 28 ; SUBROUTINE FOR TIME DELAYS OF 0.01, 0.1, 1.0,
6700: 29 ; AND 10.0 SECONDS.
6700: 30 ;
6700: 31 ;
6700: 32 ;
```

6700: 34 ;           \*\*\* HOW TO USE IT \*\*\*

```
6700: 36 ; TO USE, RUN THE DEMO BY $6700G FROM MACHINE LANGUAGE
6700: 37 ; OR CALL 26368 FROM APPLESOFT.
6700: 38 ;
6700: 39 ; THEN ADAPT THE METHOD AND RESULTS TO YOUR OWN
6700: 40 ; NEEDS.
6700: 41 ;
```

## PROGRAM RM-3, CONT'D . . .

```
6700:      44 ;          *** GOTCHAS ***
6700:      46 ; THE ACCUMULATOR IS DESTROYED BY THE WAIT SUBROUTINE.
6700:      47 ;
6700:      48 ; MACHINE TIME AND PEOPLE TIME DIFFER! ONE CLOCK CYCLE
6700:      49 ; EQUALS 0.976 MICROSECONDS, AND NOT 1.000 MICROSECONDS!
6700:      50 ;
6700:      51 ; THIS SLIGHT DIFFERENCE CAN SOMETIMES BE SIGNIFICANT.

6700:      53 ;          *** ENHANCEMENTS ***
6700:      55 ; DEMO3 ALSO SHOWS YOU SEVERAL TRICKS INVOLVED WHEN
6700:      56 ; YOU USE THE LORES SCREEN.
6700:      57 ;
6700:      58 ;
6700:      59 ;
6700:      60 ;

6700:      62 ;          *** RANDOM COMMENTS ***
6700:      64 ; IF YOU NEED AN EXACT NUMBER OF MACHINE CYCLES THAT
6700:      65 ; CANNOT BE HIT DIRECTLY WITH WAIT, TRY USING WAIT TWO
6700:      66 ; OR THREE TIMES USING DIFFERENT A VALUES.
6700:      67 ;
6700:      68 ;
6700:      69 ;
```



## PROGRAM RM-3, CONT'D . . .

```
6700:          72 ;          *** HOOKS ***

F832:          74 CLRSCR EQU $F832 ; CLEAR FULL LORES SCREEN
002C:          75 HEND EQU $2C ; RIGHT END OF LORES H LINE
C057:          76 HIRES EQU $C057 ; HIRES SOFT SWITCH
F819:          77 HLINE EQU $F819 ; HORIZ LORES LINE
FB2F:          78 INIT EQU $FB2F ; INITIALIZE TEXT SCREEN
C000:          79 IOADR EQU $C000 ; KEYBOARD INPUT
C010:          80 KBDSTR EQU $C010 ; KEYSTROBE RESET
C056:          81 LORES EQU $C056 ; LORES SOFT SWITCH
C053:          82 LOWSCR EQU $C053 ; PAGE ONE SOFT SWITCH
C052:          83 MIXCLR EQU $C052 ; FULL GRAPHICS SCREEN
F864:          84 SETCOL EQU $F864 ; SET LORES COLOR
FB40:          85 SETGR EQU $FB40 ; SET UP GRAPHICS SCREEN
C030:          86 SPKR EQU $C030 ; SPEAKER CLICK OUTPUT
C050:          87 TXTCLR EQU $C050 ; GRAPHICS ON SOFT SWITCH
C051:          88 TXTSET EQU $C051 ; TEXT ON SOFT SWITCH
002D:          89 VBOT EQU $2D ; BOTTOM OF LORES V LINE
F828:          90 VLINE EQU $F828 ; VERTICAL LORES LINE
FCA8:          91 WAIT EQU $FCA8 ; TIME DELAY SET BY ACCUMULATOR
```

## PROGRAM RM-3, CONT'D . . .

```

6700:          94 ;          *** DEMO ***
6700:          95 ;
6700:          96 ;

```

```

6700:          98 ;          THE DEMO FILLS A LORES BUCKET
6700:          99 ;          EACH SECOND TILL OVERFLOW,
6700:         100 ;          TICKING OFF EACH TENTH OF A SECOND.
6700:         101 ;
6700:         102 ;
6700:         103 ;

```

```

6700:20 0A 67 105 DEMO3 JSR DRAWCUP ; DRAW LORES CUP
6703:20 3F 67 106 JSR FILLCUP ; FILL CUP
6706:20 5C 67 107 JSR EXPLODE ; THEN EXPLODE
6709:60          108 RTS ; AND EXIT

```

```

670A:         110 ;          *** DRAWCUP SUBROUTINE ***
670A:         111 ;
670A:         112 ;          THE DRAWCUP SUBROUTINE DRAWS A LORES CUP ON THE SCREEN.
670A:         113 ;
670A:         114 ;
670A:         115 ;

```

```

670A:20 40 FB 117 DRAWCUP JSR SETGR ; INIT LORES SCREEN
670D:2C 52 C0 118 BIT MIXCLR ; FULL SCREEN GRAPHICS
6710:20 32 F8 119 JSR CLRSCR ; CLEAR FULL LORES SCREEN
6713:A9 04 120 LDA #$04 ; USE GREEN BUCKET
6715:20 64 F8 121 JSR SETCOL ; AND SET COLOR
6718:A9 19 122 LDA #$19 ; DRAW BASE
671A:85 2C 123 STA HEND ;
671C:A0 0C 124 LDY #$0C ;
671E:A9 1E 125 LDA #$1E ;
6720:20 19 F8 126 JSR HLINE ; AND PLOT IT
6723:A9 1E 127 LDA #$1E ; DRAW SIDES
6725:85 2D 128 STA VBOT ;
6727:A0 0D 129 LDY #$0D ;
6729:A9 14 130 LDA #$14 ;
672B:20 28 F8 131 JSR VLINE ; AND DRAW LEFT SIDE
672E:A9 14 132 LDA #$14 ;
6730:A0 18 133 LDY #$18 ;
6732:20 28 F8 134 JSR VLINE ; AND DRAW RIGHT SIDE
6735:A9 06 135 LDA #$06 ; SET COLOR FOR FILL
6737:20 64 F8 136 JSR SETCOL ;
673A:C6 2C 137 DEC HEND ; FILL INSIDE RIGHT
673C:C6 2C 138 DEC HEND ;
673E:60          139 RTS ; AND RETURN

```

## PROGRAM RM-3, CONT'D . . .

```
673F:      142 ;      *** FILLCUP SUBROUTINE ***
673F:      143 ;
673F:      144 ;      THIS SUBROUTINE FILLS THE CUP AT
673F:      145 ;      A ONE SECOND PER LEVEL RATE.
673F:      146 ;
673F:      147 ;

673F:A9 0A      149 FILLCUP LDA  #$0A      ; FOR TEN TRIPS
6741:8D AC 67   150          STA  CUPHI      ; SAVE INDEX
6744:20 53 67   151 AGAIN3 JSR  SECONDS     ; DELAY VIA SECONDS SUB
6747:20 A0 67   152          JSR  POUR       ; ADD TO LEVEL
674A:20 86 67   153          JSR  BRACK3     ; MAKE NOISE
674D:CE AC 67   154          DEC  CUPHI      ; NEXT CUP LEVEL
6750:D0 F2      155          BNE  AGAIN3
6752:60        156          RTS           ; AND EXIT

6753:      158 ;      *** SECONDS SUBROUTINE ***

6753:      160 ;
6753:      161 ;
6753:      162 ;
6753:      163 ;

6753:A0 0A      165 SECONDS LDY  #$0A      ; FOR TEN TENTHS
6755:20 94 67   166 NEXT3  JSR  TENTHS     ; DELAY FOR A TENTH
6758:88        167          DEY           ;
6759:D0 FA      168          BNE  NEXT3     ; REPEAT TILL DONE
675B:60        169          RTS           ; THEN EXIT
```

## PROGRAM RM-3, CONT'D . . .

```
675C:          172 ;    *** EXPLODE SUBROUTINE ***

675C:2C 57 C0 174 EXPLODE BIT HIRES ;
675F:20 9A 67 175          JSR TENMSEC ; DELAY FOR TEN MILLISECONDS
6762:2C 56 C0 176          BIT LORES
6765:20 9A 67 177          JSR TENMSEC ; AND DELAY AGAIN
6768:2C 51 C0 178          BIT TXTSET ;
676B:20 9A 67 179          JSR TENMSEC ;
676E:2C 30 C0 180          BIT SPKR ;
6771:2C 50 C0 181          BIT TXTCLR ;
6774:20 9A 67 182          JSR TENMSEC ;
6777:2C 30 C0 183          BIT SPKR ; WHAP SPEAKER
677A:2C 00 C0 184          BIT IOADR ; CHECK FOR KEYPRESS
677D:10 DD 185          BPL EXPLODE ;
677F:2C 10 C0 186          BIT KBDSTR ; RESET KEYBOARD
6782:20 2F FB 187          JSR INIT ; BACK TO TEXT SCREEN
6785:60 188          RTS ; POP STACK AND RETURN
```

```
6786:          190 ;    *** BRACK SUBROUTINE ***

6786:A0 06 192 BRACK3 LDY #$06 ; SECONDS TONE
6788:A9 0C 193 NOTE3 LDA #$0C ;
678A:20 A8 FC 194          JSR WAIT ;
678D:2C 30 C0 195          BIT SPKR ;
6790:88 196          DEY ;
6791:D0 F5 197          BNE NOTE3 ;
```

## PROGRAM RM-3; CONT'D . . .

```
6793:60      199      RTS      ;

6794:      201 ;      *** TENTHS SUBROUTINE ***
6794:      202 ;
6794:      203 ;      THIS SUB USES WAIT TO DELAY ONE TENTH
6794:      204 ;      OF A SECOND.

6794:A9 C7   206 TENTHS LDA  #$C7      ; FOR 99.415 MILLISECONDS
6796:20 A8 FC 207      JSR  WAIT      ; DELAY VIA WAIT SUB
6799:60      208      RTS      ; AND THEN RETURN

679A:      210 ;      *** TEN MILLISECONDS SUB ***
679A:      211 ;
679A:      212 ;      THIS SUB USES WAIT TO DELAY TEN MILLISECONDS.
679A:      213 ;

679A:A9 3D   215 TENMSEC LDA  #$3D      ; FOR 99.415 MILLISECONDS
679C:20 A8 FC 216      JSR  WAIT      ; DELAY VIA WAIT SUB
679F:60      217      RTS      ; AND THEN RETURN

67A0:      219 ;      *** POUR SUBROUTINE ***
67A0:      220 ;

67A0:18      222 POUR   CLC      ; FILL CUP WITH LIQUID
67A1:A9 13   223      LDA  #$13      ; TOP OF CUP LEVEL
67A3:6D AC 67 224      ADC  CUPHI     ; MINUS HEIGHT ALREADY
67A6:A0 0E   225      LDY  #$0E      ; LEFT SIDE SET
67A8:20 19 F8 226      JSR  HLINE     ; DRAW LEVEL
67AB:60      227      RTS      ; AND EXIT

67AC:      229 ;      *** STASH ***

67AC:0A      231 CUPHI  DFB  $0A      ; LEVEL IN CUP
```

\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS

## OBNOXIOUS SOUNDS

**an extremely versatile and compact wide-range sound-effects generator**

First the bad news.

For a given amount of programming effort and add-on hardware, the Apple will always give you sound that is "thin" and animation that is "weak," when compared against an arcade video game. This happens inevitably because the Apple CPU has to take time out to generate its own sound and graphics, and because the color system is stuck with being more or less compatible with the NTSC ("Never The Same Color") broadcast television standard.

The good news, of course, is that for an extraordinary amount of creative programming effort, and for super creative use of extra hardware, you can use your Apple to knock the bytes out of any arcade video game or any other brand of personal computer. All it takes is lots of special effort that optimizes what you can do within the bounds of the actual limits of your Apple.

The next two ripoff modules show us two of the many different ways you can get sound into your programs. We will assume, for now, that you are going to use the built-in speaker of an unmodified Apple.

The "noisemaking" hardware of your Apple seems rather limiting at first glance. You have one small and tinny-sounding speaker. All the support hardware lets you do is shove the speaker cone all the way in,

or else pull it all the way out. You do this by “whapping” address location \$C030 *once* each time you want to *change* the cone’s position.

Technically, address \$C030 is decoded and used to change the state of a binary divider, or flip-flop. The flip-flop is coupled to a special Darlington driver transistor. One whap pushes the cone in. The next pulls it out . . .

**A BIT \$C030 is the standard way of moving the Apple speaker’s cone from the extreme position it is in to the other extreme position.**

To get some useful sounds out of the Apple speaker, you decide how often you want to shove the cone back and forth, and carefully pick the time delay needed between shovings. For instance, if you keep a constant time between shovings, you will set the pitch of an audio square wave. The duration of the tone is decided by how long you continue the shoving process.

Believe it or not, you can easily get more than one note at once, have variable volume, do bell-like tones, handle speech, and do much, much more if you are a sneaky enough programmer. And your sound can be further “thickened” considerably just by adding a larger speaker to your Apple.

Before getting fancy, though, let’s get two gotchas out of the road . . .

**\$C030 GOTCHAS**

two whaps immediately following each other give you no sound . . .

**USE BIT \$C030, NOT STA \$C030.**

one isolated whap may not sound . . .

**USE AT LEAST 3 WHAPS PER CLICK.**

Due to a quirk in the Apple’s timing, any time you write to a memory location, you address that location twice. The two addressings are separated by one microsecond. If you try to do a STA \$C030, you end up shoving the speaker in and then pulling it back out again an impossibly brief time later. The cone barely moves in so short a time, and, surprise, surprise, you get no sound.

So, always BIT test your speaker location. Do not write to it, unless you want no sound.

The second quirk comes about because of an attempt to save Apple system power. There is a coupling capacitor in the path between the flip-flop and the speaker. This capacitor discharges on inactivity. Which means that the speaker cone is never held “in” for long periods of time. The dropout time is long compared to most tones, so you normally won’t notice it.

There are two places where you might pick up the side effects of this power-down capacitor, and where it may cause you trouble. If you try to “click” the speaker just once, there’s only a 50-50 chance you will get any sound at all. So, it takes two repeated commands, delayed by some audio value, to guarantee an isolated click. In real life, three or four repeated speaker motions are the minimum you will want to use, since some of the clicks will sound “leaner” than others.

The other place this gotcha appears happens when you send very low-pitched notes, or a very low-pitch “sweep” to your speaker. At some point, the frequency will jump up by an octave. This frequency doubling happens when the capacitor picks up enough charge to allow cone clicking in both directions.

Watch these two details if you ever get no sound or uneven sound out of your code.

As in all other Apple programming techniques, there are lots of different ways to get sound, and each of these ways will have a certain range of effects over which they are useful. Let’s survey some . . .

WAYS TO GENERATE APPLE SOUND
clickety clack calculated routine red book tones  table method duty cycling offloading

With the *clickety clack* method, you simply move the speaker cone back and forth a few times, using a loop or some other obvious code. See the BRACK subroutine of the previous ripoff module for an example. The time between whappings sets the pitch while the total number of whappings sets the duration of your sound. If the pitch is constant, you get a “pure” tone. If the pitch changes, you get a “sweep.” If both halves of each cycle are the same time duration, you get a “woodwind” style tone. If one half of each cycle is much longer than the other, you get a “string” style voicing.

One important exception to the clickety clackers. Do not ever use the standard “[G]” or “[JSR \$FF3A]” beep. This tone is too grating to ever use in any reasonable program . . .

<p><b>NEVER</b> use the “standard” Apple beep anywhere in any of your programs!</p> <p><b>ALWAYS</b> kick sand in the face of anyone who does.</p>
--

In the *calculated routine* method, you generate some code that decides when and where all the zero crossings are needed for a certain sound effect. This method is often used for sirens and sweeps,



tonal scales, frog croaks, phasors, and other short or weird "one-shot" sounds.

The good thing about the calculated routine method is that you can get some real serendipity going, and end up with some totally wild sounds that you wouldn't ever have thought possible otherwise. The bad scene about many calculated routines is that this is "old" code done the "old" way that may end up long and cumbersome, rather than short and general.

The OBNOXIOUS SOUNDS subroutine of this ripoff module will shortly explore this technique.

The *red book tones* method is a way to make monophonic music that is useful for playing songs in tempered musical scales. This involves a pitch and duration generator, and some file access tricks. More on this in the next module.

The *table method* looks up each speaker motion as needed, out of a long table. You can produce *any* possible sound this way. Most Apple-based speech uses the table method, and virtually any sound of most any complexity can be handled with a general and versatile enough program.

There are some tricks to using the table method. Getting the table to sound like you really want it to can be very involved and may take a long time. Finding some suitable coding that lets you put lots of sound in a short table is also a real hassle. Long or multiple effects really burn up the bytes. The obvious brute force method of storing a one each time you want the speaker to move can be substantially improved by going to some sort of "run length" encoding.

The best way to study table method sound is to steal the German vocabulary file out of *Castle Wolfenstein*. To grab this table, just follow the "tearing" method of Enhancement 3 in the *Enhancing Your Apple II*, Volume I (Sams 21822).

Ah yes. Duty Cycling.

Pushing the limits. Doing the impossible. How on earth can you get more than one tone at a time out of a speaker driver that you can only push or pull? How can you do variable volume? Sinewaves and flute-like or bell-like tones?

Its really very simple. Suppose you *extremely rapidly* move the speaker cone in and out, at an ultrasonic rate. The average cone position depends on the average duty cycle. For a sinewave, just let the average cone position describe a sinewave at the frequency you want. For bell tones, let the average position slowly "decay" to its "middle" value. For more than one note at once, just let the average position equal the sum of all the notes taken together at once.

If you get into some hairy math involving *Fourier coefficients*, you can easily handle chords and other multitone effects, with or without duty cycling. The whole trick is to, on the average, put the speaker cone where it ought to be when it ought to be there.

Duty cycling techniques are described in various issues of *Apple Assembly Line*.

Offloading consists of using something other than the Apple's speaker to make the noise. Simply going to a larger speaker or into a hi-fi will help "thicken" the sound bunches, and you can get stereo effects by using the speaker hardware for one channel and the cassette output port for the other. You can separately get four more channels out of the annunciator outputs of your game paddle connector.

But the real benefits of offloading take place when you send simple commands to a custom noise generator or music generator chip. Besides producing much richer and more flexible sounds, you now offload the Apple's CPU so it is free to go on to other things. All the Apple has to do is quickly pass a few parameters on to the music chip, rather than stalling around for the entire time it takes to produce the entire tone or tone sequence.

Both *General Instruments* and *Texas Instruments* are heavily into music and sound-effect generation chips. These are often the key circuits used in the fancier plug-in synthesizer cards and systems as well.

Time now for more details on . . .

### The Calculated Routine Method

The calculated routine method is best done for single and isolated sound effects.

A phasor blast, of course, is the architypical example of this sort of thing. We'll show you a few dozen bytes of code that do the standard and classical phasor blast for you. But, by changing only two values, those same bytes can do a surprising variety of effects that sound wildly different.

These include some very pleasant and highly "brassy" prompt tones, musical glissades, some "cartoon" style sound, a geiger-counter simulation, and a few assorted and highly useful pips, ticks, and whopidoops. There's even a special effect called the *time bomb*, that lasts for minutes, and has all sorts of impractical joke possibilities.

The object of *any* sound program is to produce some speaker whappings separated by some time delays. The time delays set the time between zero crossings of the sound that the speaker is to produce. Usually these delays will range from 10 microseconds to 10 milliseconds or so. Faster than this and you are into ultrasonics that you cannot hear and that the speaker cone cannot follow. Slower than this breaks the sound down into individual and possibly annoying clicks.


If all the time delays are the same value, you get a constant square-wave tone. The total number of time delays sets the duration of the tone, while each individual delay sets the pitch of each half-cycle of sound.

Things get interesting when you vary the time delays in a strange manner. For instance, if you make each successive time delay shorter, you get a siren or sweep effect that goes up in time.

The whole intent of the calculated routine method is to produce some interesting changes in the time delays that give you fat, thick, and interesting sound effects. The calculations of your routine should create a group of delay values that result in a useful sound.

Here's the flowchart for this module's calculated routine sound effects generator . . .

**OBNOXIOUS SOUNDS FLOWCHART:**



Actually, this is nothing but a very simple sweep generator with one or two added tricks. The only two parameters under your control are how far you sweep and the total number of sweeps you use. Now,

don't go away, for you will be utterly amazed at how many *totally different* effects you can get this way. In theory, there are 65536 different effects possible. In practice, there's only two dozen or so that you will find genuinely useful and uniquely different.

Our first trick is to use the monitor delay subroutine. Remember that these delay values are "cramped together" at the short end, giving you a more or less log response. And this is just what you want for an audio sweep. A linear sweep sounds awful, since your ear is a log device that expects a few cycles change for low notes and lots of cycles change for high notes. So, the monitor delay sub automatically puts the low notes close together and the high notes far apart, just like you need.

Our second trick is to use the same value to set both the pitch and the length of each step in the sweep. This keeps things simple, yet still gives you many different sounds.

Our third trick is very sneaky. Five testing bytes are added to give you geiger counter or multiple click effects. If the sweep duration is *less* than \$80, you get the complete sweep, all the way up in pitch. If the sweep duration is *greater* than \$80, the sweep only goes to the \$80 value and then quits.

The \$80 value is extremely low in pitch. So low that you hear each cone movement as a distinct click. With the five byte code patch, values greater than \$80 give you a burst of clicks. Values less than \$80 give you the full sweep. So, you get two wildly and totally different classes of sound effects out of the same simple calculated routine.

We have used a sixteen-entry file to support the sound effects generator. If you only want one or two sounds, you can eliminate this file and direct poke the effects you are after. Each sound effect is specified with two values. The first decides the *number* of the sweeps produced, while the second decides *how long* each sweep is to be.

At any rate, you enter the subroutine with a number in the X register that equals the sound effect you are after. You then save all the other registers. Next you check to make sure the number is legal. If it is not, you replace it with sound effect zero. You might prefer some fancier error trapping here, but this is probably all you will really need.

Next, the sound effect number is converted into two sweep values by looking them up in the SEF effects file. The number of sweeps is grabbed first and put in an absolute location called TRPCNT4. This location will get counted down, once per each complete sweep. After this, the sweep duration is grabbed and "force fed" into the code at SWEEP4+1.

Uh, whoops. Play that one by again.

Tricks like this go by the name of *self-modifying* code. Which is legal and powerful if you know what you are doing. What you have done here is *changed* a LDY #00 command into a LDY #SWEEPS command. Note that the data value gets poked into the *second* byte of the op code! Put it anywhere else and you plow the program. Note also that any self-modifying code *must* be in RAM. EPROM need not apply.

Why?

Generally, it is safe to *pre-modify* your code like we have done here. In fact, this is a standard and powerful programming technique. Just be sure that you are changing *ONLY* the EXACT location you think you are. On the other hand, code that continuously changes itself on

the fly is very dangerous. Deadly even. Yet still a specialized and most useful programming technique.

Some comment . . .

**If you self-modify code, be sure to place what you are putting EXACTLY where you intend to put it!**

**One or two data values preplaced once before use is safe and standard.**

**Code that continuously changes itself is often dumb and deadly.**

So much for a side trip on self-modifying code. At this point, we have a "number-of-sweeps" value in TRPCNT4, and the "length-of-the-sweep" value has been force fed into a command that loads the Y register.

Now to get sneaky. We need a third parameter. Namely, the duration value that sets the frequency for this part of our sweep. For simplicity, we just transfer Y to X, and let X set our duration and Y our pitch. For any given step of our sweep, we want all constant frequencies. Thus, we will keep Y constant while we count X down. This results in a sound that sweeps up in distinct note-like steps.

So far, so good. You transfer your pitch value to the accumulator and then use the monitor delay to stall for a half-cycle. Then, you whap the speaker. Next, you check X for the \$80 value that separates the geiger effects from the long sweeps. If you have a geiger burst, you exit. For a sweep, you continue.

You continue this for X half-cycles to generate one "step" of your sweep. Then you decrement Y to go on to the next sweep step. Do this till you have completed the last step. Note that the last step is the shortest and the highest in pitch.

That should complete one sweep for you. Decrement TRPCNT4. If more sweeps are needed, then repeat the process for as many sweeps as you want. Finally, restore all the registers and exit.

There is an "oldfangled" classic cell animation demo on the companion diskette named ENGINE that you simply will not believe the first time you see and hear it. ENGINE uses the obnoxious sounds subroutine. It also has two secret ingredients called David W. Meyer, Sr., and David W. Meyer, Jr. Who, together, form one of the most fantastic father and son Apple animation teams I've ever run across anywhere, ever. And, yes, they do custom work. See the Appendix for an address.

We'll show you a simpler demo of the obnoxious sounds here and now. DEMO4 just goes through all sixteen of the sounds in order and gives you a time delay between effects.

DEMO4 produces an earth-shattering explosion a second or so after the time bomb countdown is complete. Be sure to remove all china, Ming vases, etc. from a thousand-foot radius of your Apple before running this demo.

**MIND BENDERS**

- Change the code so you sweep down rather than up. Do you like this?
- Extend the code so you can control pitch separately from step duration.
- What can you do with a pair of sweeps that interact with each other?
- Add suitable graphics to the time bomb.
- Which obnoxious sounds are used how in ENGINE? How is flawless animation and thick sound achieved at the same time?
- How is the frog's voice produced in RIBBIT?

**PROGRAM RM-4  
OBNOXIOUS SOUNDS**

----- NEXT OBJECT FILE NAME IS OBNOXIOUS SOUNDS

6800:           3           ORG \$6800           ; PUT MODULE #4 AT \$6800

```

6800:           5 ; *****
6800:           6 ; *
6800:           7 ; *           -< OBNOXIOUS SOUNDS >- *
6800:           8 ; *
6800:           9 ; *           (CUSTOM CODING METHOD) *
6800:          10 ; *
6800:          11 ; *           VERSION 1.0 ($6800-$687F) *
6800:          12 ; *
6800:          13 ; *                           11-24-82 *
6800:          14 ; *.....*
6800:          15 ; *
6800:          16 ; *           COPYRIGHT C 1982 BY *
6800:          17 ; *
6800:          18 ; *           DON LANCASTER AND SYNERGETICS *
6800:          19 ; *           BOX 1300, THATCHER AZ., 85552 *
6800:          20 ; *
6800:          21 ; *           ALL COMMERCIAL RIGHTS RESERVED *
6800:          22 ; *
6800:          23 ; *****

```

6800:           25 ;           \*\*\* WHAT IT DOES \*\*\*

```

6800:           27 ;       THIS MODULE GENERATES SIXTEEN DIFFERENT SOUND EFFECTS
6800:           28 ;       FOR USE INSIDE ANOTHER PROGRAM.
6800:           29 ;
6800:           30 ;
6800:           31 ;
6800:           32 ;

```

6800:           34 ;           \*\*\* HOW TO USE IT \*\*\*

```

6800:           36 ;       TO USE FROM MACHINE LANGUAGE, LOAD THE X REGISTER WITH
6800:           37 ;       A SOUND SELECTION FROM $00 TO $1F AND THEN JSR TO $6824.
6800:           38 ;
6800:           39 ;       TO USE FROM APPLESOFT, POKE 26659 WITH THE SOUND
6800:           40 ;       EFFECT FROM 0-15 AND CALL 26658.
6800:           41 ;

```

## PROGRAM RM-4, CONT'D . . .

```
6800:      44 ;          *** GOTCHAS ***
6800:      46 ; THE X REGISTER IS DESTROYED BY THIS SUBROUTINE.
6800:      47 ; REGISTERS P,Y, AND A ARE SAVED FOR YOU.
6800:      48 ;
6800:      49 ; THE PROGRAM MUST BE PLACED IN A PROTECTED AREA
6800:      50 ; IF IT IS TO BE USED BY EITHER BASIC.
6800:      51 ;

6800:      53 ;          *** ENHANCEMENTS ***
6800:      55 ; YOU CAN CHANGE THE EFFECTS BY CHANGING THE TRIP AND
6800:      56 ; SWEEP VALUES FOR EACH FILE SELECTION. SEE THE
6800:      57 ; EFFECT FILE LISTING FOR PRESENTLY AVAILABLE EFFECTS.
6800:      58 ;
6800:      59 ; EXTRA TONES ARE EASILY ADDED BY LENGTHENING THE SOUND
6800:      60 ; EFFECT FILES SEF0-SEF15 AND CHANGING FLNGTH4

6800:      62 ;          *** RANDOM COMMENTS ***
6800:      64 ; TO ACTIVATE THE DEMO PROGRAM THAT PLAYS ALL SIXTEEN
6800:      65 ; NOTES IN ORDER, USE JSR $6800 OR CALL 26624.
6800:      66 ;
6800:      67 ;
6800:      68 ;
6800:      69 ;
```



## PROGRAM RM-4, CONT'D . . .

```

6800:          72 ;          *** HOOKS ***

FC58:          74 HOME      EQU  $FC58      ; CLEAR SCREEN
FB2F:          75 INIT      EQU  $FB2F      ; HOME CURSOR
C030:          76 SPKR      EQU  $C030      ; SPEAKER CLICK OUTPUT
FCA8:          77 WAIT      EQU  $FCA8      ; TIME DELAY SET BY ACCUMULATOR

6800:          79 ;          *** DEMO ***
6800:          80 ;
6800:          81 ;

6800:          83 ;          THE DEMO PROGRAM PLAYS EACH OF THE SIXTEEN
6800:          84 ;          SOUND EFFECTS IN ORDER, SEPARATED BY A
6800:          85 ;          TIME DELAY.
6800:          86 ;
6800:          87 ;
6800:          88 ;

6800:20 2F FB   90 DEMO4    JSR  INIT      ; MAKE SCREEN BLANK
6803:20 58 FC   91          JSR  HOME      ;
6806:A9 00      92          LDA  #$00      ; START WITH FIRST NOTE
6808:48          93          PHA           ; AND SAVE ON STACK

6809:AA          95 NXTNOT4  TAX           ;
680A:20 24 68   96          JSR  OBNOX4    ; AND PLAY IT
680D:A0 0A      97          LDY  #10      ; STALL FOR TIME

680F:20 A8 FC   99 STALL4   JSR  WAIT      ;
6812:88          100         DEY           ;
6813:D0 FA      101         BNE  STALL4    ; TILL DELAY DONE

6815:68          103         PLA           ; GET NOTE NUMBER
6816:CD 5F 68   104         CMP  FLNGTH4  ; DONE WITH LAST NOTE?
6819:F0 06      105         BEQ  DONE4    ; YES, EXIT

681B:18          107         CLC           ;
681C:69 01      108         ADC  #$01     ; NO, PICK NEXT NOTE
681E:48          109         PHA           ;
681F:D0 E8      110         BNE  NXTNOT4   ; ALWAYS

6821:60          112 DONE4   RTS          ; AND EXIT

```

## PROGRAM RM-4, CONT'D . . .

```

6822:      115 ;          *** OBNOX MODULE ***
6822:      116 ;
6822:      117 ;

6822:      119 ;          THIS MODULE GENERATES THE SOUND EFFECTS IN
6822:      120 ;          EXCHANGE FOR AN X VALUE FROM $00 TO $0F.
6822:      121 ;
6822:      122 ;
6822:      123 ;
6822:      124 ;

6822:A2 00      126 BASENT4 LDX  #$00      ; BASIC POKE HERE+1
6824:08      127 OBNOX4  PHP              ; ML ENTRY POINT
6825:48      128          PHA              ;
6826:98      129          TYA              ; SAVE P,A, AND Y REGS
6827:48      130          PHA              ;

6828:8A      132          TXA              ; RANGE CHECK ON SELECTION
6829:CD 5F 68 133          CMP  FLNGTH4    ; TO MAKE SURE ITS IN FILE
682C:90 02      134          BCC  LOK4      ;
682E:A9 00      135          LDA  #$00      ; DEFAULT TO ZERO SELECTION
6830:0A      136 LOK4     ASLA              ; AND DOUBLE FILE POINTER
6831:AA      137          TAX              ;
6832:BD 60 68 138          LDA  SEF0,X     ; GET NUMBER OF TRIPS
6835:8D 5E 68 139          STA  TRPCNT4    ; AND SAVE
6838:E8      140          INX              ;
6839:BD 60 68 141          LDA  SEF0,X     ; GET SWEEP RANGE
683C:8D 40 68 142          STA  SWEEP4+1   ; AND SAVE

683F:A0 00      144 SWEEP4 LDY  #$00      ; SWEEP VALUE POKED HERE
6841:98      145 NXTSWP4 TYA              ;
6842:AA      146          TAX              ; DURATION
6843:98      147 NXTCYC4 TYA              ; PITCH
6844:20 A8 FC 148          JSR  WAIT       ;
6847:2C 30 C0 149          BIT  SPKR       ; WHAP SPEAKER
684A:E0 80      150          CPX  #$80     ; BYPASS IF GEIGER
684C:F0 0B      151          BEQ  EXIT4    ; SPECIAL EFFECT
684E:CA      152          DEX              ;
684F:D0 F2      153          BNE  NXTCYC4   ; ANOTHER CYCLE
6851:88      154          DEY              ;
6852:D0 ED      155          BNE  NXTSWP4   ; GO UP IN PITCH
6854:CE 5E 68 156          DEC  TRPCNT4    ; MADE ALL TRIPS?

6857:D0 E6      158          BNE  SWEEP4    ; NO, REPEAT

6859:68      160 EXIT4   PLA              ; RESTORE REGISTERS
685A:A8      161          TAY              ;
685B:68      162          PLA              ;
685C:28      163          PLP              ;
685D:60      164          RTS              ; AND EXIT

```

## PROGRAM RM-4, CONT'D . . .

```
685E:          167 ;          *** STASH ***

685E:01        169 TRPCNT4 DFB $01      ; TRIP COUNT DECREMENTED HERE
685F:10        170 FLNGTH4 DFB $10      ; SIXTEEN AVAILABLE SOUNDS

6860:          172 ;          *** SOUND EFFECT FILES ***

6860:          174 ;          EACH NOTE TAKES A TRIP AND A SWEEP VALUE IN SEQUENCE.
6860:          175 ;
6860:          176 ;          ADD $80 TO NUMBER OF GEIGER CLICKS WANTED.
6860:          177 ;
6860:          178 ;
6860:          179 ;

6860:01 08     181 SEF0      DFB $01,$08 ; TICK
6862:01 18     182 SEF1      DFB $01,$18 ; WHOPIDOOP
6864:FF 01     183 SEF2      DFB $FF,$01 ; PIP
6866:06 10     184 SEF3      DFB $06,$10 ; PHASOR
6868:01 30     185 SEF4      DFB $01,$30 ; MUSIC SCALE
686A:20 06     186 SEF5      DFB $20,$06 ; SHORT BRASS
686C:70 06     187 SEF6      DFB $70,$06 ; MEDIUM BRASS
686E:FF 06     188 SEF7      DFB $FF,$06 ; LONG BRASS
6870:01 A0     189 SEF8      DFB $01,$A0 ; GEIGER
6872:FF 02     190 SEF9      DFB $FF,$02 ; GLEEP
6874:04 1C     191 SEF10     DFB $04,$1C ; GLISSADE
6876:01 10     192 SEF11     DFB $01,$10 ; QWIP
6878:30 0B     193 SEF12     DFB $30,$0B ; OBOE
687A:30 07     194 SEF13     DFB $30,$07 ; FRENCH HORN
687C:50 09     195 SEF14     DFB $50,$09 ; ENGLISH HORN
687E:01 64     196 SEF15     DFB $01,$64 ; TIME BOMB
```

\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS

## MUSICAL SONGS

**an upgrade of the original “red book tones” song and music maker**

Come on, kiddies. If you are going to reinvent the wheel, please make the thing roughly circular and put an axle somewhere near the middle, preferably pointing in some more or less reasonable direction.

The wheel in this case is a music machine that easily and simply gives you an audio tone in exchange for pitch and duration values. There are so many utterly atrocious attempts at this that it is no longer even funny.

In particular . . .

**A music making subroutine MUST have totally separate and totally isolated ways of entering pitch and duration.**

**ANYTHING ELSE ISN'T EVEN WRONG!**

If the duration of your note changes when you change the pitch, your music maker is less than worthless. Flush it.

It turns out that a really great music making subroutine has existed since year one that uniquely solves the pitch and duration interaction

problem. The sub is called the *red book tones*, Woz wrote it, and it appears, of all places, in the original red book.

The red book tones are a “middleweight” technique that lets you create reasonable sounding monophonic music, as well as providing an easy way to pick up lots of different cue and prompt tones for other program uses. The original code, as it first appeared, was all of twenty-one bytes long!

Today, of course, you cannot write commercial software and get away with monophonic, fixed timbre, or constant volume sound effects. Use of multiple voices, variable volume, and duty-cycling is absolutely mandatory. But, just as LORES is an essential stepping stone to commercially useful graphics, the red book tones are a necessary learning experience along the way to top-notch musical effects.

While we will not be reinventing the wheel, we are going to add a hubcap, some chrome, and better bearings.

First, we all call the newer version REDTONE. As with the original, it gives you a constant frequency square-wave tone in exchange for pitch and duration values. We’ve put REDTONE into source code so you can relocate it anywhere you want. The original code sat on page zero and had some Applesloth compatibility problems. The obvious choice of page three is so overloaded these days, that it is best to have something you can put anywhere you want.

REDTONE saves all the working registers to avoid conflicts with your high level code. The pitch and duration values are also saved for you, so you needn’t reload the same duration value over and over again for cues or prompts.

There is now a *silent* pitch value of \$FF. This is most handy for rests and pauses. The silence is timed out to the same duration value any other note would be. As a convenience, the notes are echoed to the cassette output port. You can greatly improve the sound by going through a small hi-fi amplifier and larger speaker. Use standard audio cables.

The maximum duration on the original code was a little short, particularly when it came to playing whole notes at low tempos, so REDTONE has a feature called a *duration multiplier* that lets you extend the duration in binary multiples. You now have all the duration range you could possibly ever use, plus a ridiculous bunch more.

And that just about covers the code improvements. We’ve also made two use improvements. The first involves better pitch accuracy, and the second lets your Assembler enter music in a sane and more or less musical way. For instance, a half note of middle C is entered as “C1,H,”. There are no worries about funny numbers.

Tempo is presently set by changing a single value before assembly. You can easily upgrade to a “real time” tempo control. I’ve purposely left this as an “exercise for the student.”

## **Pitch Accuracy**

Most people try to set up a tone generator to make some certain pitch exactly hit some musical note. Then they go up and down the scale from there, trying to “fit” the notes to the 8-bit pitch values needed.

The problem is that this technique works well for some notes and poorly for others. Some notes just won’t fit and will sound out of tune.

Some review. An octave is a 2:1 frequency change, and is just about as far as you can easily reach on a piano, say from middle C to the next higher C. People have messed with how many notes go where for a long time, but today, most everyone uses a compromise system called the *equally tempered* scale.

The equally tempered scale has twelve notes per octave. The notes in the “key” of C are called, C, C#, D, E, F, F#, G, G#, A, A#, B, and back again to the next C that’s one octave higher. Note that there is no “E#” or “B#” as such. Other keys may name these notes differently and may start at a different point, but regardless of which key is in use, there are only twelve notes per octave.

The pitch of a note is related to that note’s frequency, which is called out in hertz, or cycles per second. For instance, the pitch of the A above middle C is standardized to a frequency of 440 Hz.

Since the ear is a logarithmic type device, it expects low frequency differences between notes for the low notes, and high frequency differences between notes for the high notes. If you tried to create a linear “scale” that went, say 300, 350, 400, 450, 500, . . . etc. Hz, it would sound very weird indeed.

Unmusical, even.

To get a log spacing of 12 notes over one octave, each successive *equally tempered* note has to be the *twelfth root of two* higher in frequency. This is roughly a factor of 1.06. Each note ends up roughly 6 percent higher in frequency than its neighbor.

The interval from note to note is called a *semitone*. A semitone is the difference from one key to the immediate next one on a piano, regardless of key color. A semitone is also a 6 percent increase in frequency. A pitch change of one semitone is thus only a few hertz for low notes, but is very much more than this for high notes.

How accurate do the tones have to be? It turns out that very few people have what is called “absolute pitch,” so if the whole song is uniformly mistuned too high or too low, nobody will be able to tell.

What counts is the relation between the notes, or “relative pitch,” and here, things get sticky fast . . .

**Few people can tell ABSOLUTE PITCH, so it really doesn’t matter whether all the notes are exactly set to their intended absolute frequencies.**

**Just about anybody can tell RELATIVE PITCH, so it is super important that the notes all sound good together.**

Thus, if an “A” is really 480 Hz rather than 440, the odds are high that nobody will notice on a stand-alone song. So long, of course, that all the *other* notes are equally offset from where they belong *by the same proportion*. What is critical is the *relative* frequency difference between “A” and “A#,” or between any other notes.

How critical is critical? Musicians call one one-hundredth of a semitone a *cent*. A one cent frequency error is an error of just under 0.06 percent in the ratio of two notes. It turns out that the best musicians can just barely spot a one cent frequency error, while an average careful listener can spot a three cent error.

The trick is to get accurate relative notes consistent with a pitch word that is only 8 bits wide. If you just force any old note to be exact and then try to find magic values for the other notes, one or more of them will sound sour.

If you play with funny numbers long enough, you'll find that there is a little known but super important series of 8-bit pitch values that give far and away the most accurate notes you can possibly get using 8-bit values. Any other attempt at pitch values will fall short of this optimum series, and you'll get several sour notes.

Here's the magic series and the notes involved . . .

<b>"MAGIC" 8-BIT PITCH VALUES</b>	
232	(A)
219	(A#)
207	(B)
195	(C)
184	(C#)
174	(D)
164	(D#)
155	(E)
146	(F)
138	(F#)
130	(G)
123	(G#)
116	(A)

These notes are all accurate to better than three cents in relative pitch. Once again, this is a "magic" series. Any other choice of pitch values will give you at least one sour note. Note that the pitch values will set the time between speaker motions of REDTONE, so the *higher* the pitch value, the *lower* the pitch or frequency of the note you get. It takes two shoves, one forward and one backward, of the speaker cone, to generate one full cycle of a REDTONE square wave. The timbre you get is a "woody" one roughly akin to a clarinet or a stopped organ pipe.

The approximate notes you actually get with REDTONE are shown in parentheses. You can continue up in pitch, but you'll eventually pick up some sour notes on the way. Just divide each of the "magic" values by two for the next octave, and so on.

Note that you will only have seven or fewer bits of accuracy for these higher notes. Which means a few of them may be off in pitch. By the way, you also have an additional magic 8-bit pitch value of 246. This translates to a REDTONE "G#" or "Ab," and it seemed to make more sense to start at "A" instead.

**Separating Pitch and Duration**


The "obvious" way to generate a tone is to count one register down to get the pitch. Each completed countdown whaps the speaker once. To get duration, you then count the total number of whappings.

Which is simple but wrong.

The trouble is that the high notes will sound much shorter than the low notes. Which gets to be a real mess. Any decent music maker subroutine *must* separate pitch and duration.

Here's how to do it . . .

### USING A "SERVICE" LOOP TO SEPARATE PITCH & DURATION:



What you do is set up a tight *service loop* that *continuously* tests *both* the pitch and duration values. Two counters are involved, an 8-bit pitch counter, and a 16-bit or longer duration counter. The service loop continuously decrements *both* of these counters. When the magic pitch value is hit, the speaker gets whapped. When the magic duration value is hit, the tone ends. Since the duration values are usually much larger than the pitch values, you will normally get many pitch cycles in your note.

The way the original red book tones got its 16-bit duration values was to take an 8-bit duration value and multiply it by 256 using the Y register. Thus, the Y register had to go all the way around for each count of the duration counter.



All of which elegantly solved keeping pitch and duration separate.

### A Duration Multiplier

The only little problem with this scheme was that 16 bits worth of duration weren't quite enough for some uses. Things were OK for simple songs, but for dotted half notes or for whole notes played at slow tempos, there simply wasn't enough duration to fully sound the note. The maximum duration was just under one second.

REDTONE gets around this by going to as many as 24 bits for the duration counter. It turns out that REDTONE never needs the accumulator, so this register is free to be used as a multiplying counter.

Here's how it works. You always initialize the accumulator to \$00. Now, say you add some magic value to the accumulator and test for zero. The results you get depend on what you add. Four useful results include . . .

**Adding \$00 gives you**

00 00 00 00 00 00 00 00 00

and multiplies by ONE.

**Adding \$80 gives you**

00 80 00 80 00 80 00 80 00

and multiplies by TWO.

**Adding \$40 gives you**

00 40 80 C0 00 40 80 C0 00

and multiplies by FOUR.

**Adding \$20 gives you**

00 20 40 60 80 A0 C0 E0 00


and multiplies by EIGHT.

What you do is count down the duration counter every time you get a zero result. Thus, the \$40 adder only decrements the duration counter on every *fourth* trip through the service loop. This makes the note last four times longer.

Usually, a "X2" multiplier is just what you need for most music. You can go up to "X256" multiplication, using an \$01 magic value, if you want to get ridiculous.

With these details out of the way, let's look at the REDTONE subroutine. Here's the flowchart . . .

## REDTONE FLOWCHART:



You enter REDTONE with a pitch value of PITCH5 and a duration value of DURAT5. These values are not destroyed should you want to reuse them for simple prompts. You must also have a multiplier value

in DURMULT5, but leaving this value at \$80 will give good results for most uses.

The registers are first saved. Then DURAT5 is copied into DURCNT5 where it can be counted down. The copying saves you having to reenter the same duration each time for simple prompts. This is followed by clearing the Y register and the accumulator. The accumulator will be used for the duration 1-2-4 multiplier, while the Y register will be used to scale the duration by 256. You can alternately use the Y register to adjust tempo in real time.

The pitch value is placed in the X register and tested. If the pitch is not \$FF, the note is accepted and processed as usual. The speaker is then whapped, and then is echoed to the cassette output.

Next, the service loop takes over. First, the Y register is decremented. If Y hits zero, then the duration multiplier gets activated, by adding the multiplier value and testing for a zero result. If the Y register has gone all the way around and if the duration multiplier gives you a zero result, then, and only then, is DURCNT5 decremented. Note that this has the effect of multiplying the DURCNT5 value first by 256 and then by the accumulator multiplier of 1, 2, 4, or whatever.

If we have not gotten a zero duration value, we then knock one off the pitch counter and repeat the service loop process. The speaker gets whapped only on zero values of the pitch counter. Thus a single service loop separately keeps track of pitch and duration with only negligible interaction.

Note that the duration is the product of three 8-bit values. Duration is set by multiplying the Y register *times* DURAT5 *times* DURMULT5.

Every pitch zero, the speaker gets hit, and the X register gets reloaded with a new pitch value. The only exit from all this happens when DURCNT5 finally hits zero. At that point, the registers are restored and the subroutine exits to your calling code.

One final detail. If your chosen pitch value is \$FF, the speaker is not sounded. This gives you a silent note, a pause, or a rest.

The side loop at LOCKX handles this detail for you. If the pitch is \$FF, the pitch is incremented to \$00 by LOCKX, and then later decremented back to \$FF in the main service loop. Thus a \$FF pitch value stays at \$FF all the way through the duration timing. This happens because  $\$FF + \$01 - \$01 = \$FF$ . A sounding pitch value gets counted down to zero and whaps the speaker every trip. A silent pitch value stays at \$FF and bypasses the speaker, producing no sound.

## **A Demo or Two**

The SONGPLY demo exercises REDTONE for you, playing that ever favorite song that Tarzan used to sing during his zebra maintenance days. SONGPLY works by picking pitch and duration value out of a songfile called TARZAN.

We have used a 16-bit full wide pointer to access the song file, so you can have more than 128 notes total in your song. This pointer is called NOTEP and is page zero stashed at \$EF and \$F0. To link SONGPLY to different songs, you change these pointers as needed.

The pause generator inside SONGPLY gives you a brief pause between notes that is set by PAUSE. Experiment to get the best results. The minimum PAUSE value is \$01. Do not use \$00!

Should your particular song demand some notes that slur or tie together, just use a minimum value of PAUSE, say \$01. Then use sixteenths rests or whatever between those notes that do not slur.

Be sure to study the source code on SONGPLY very carefully, for it shows you a fairly friendly way to use labels to simplify writing your own songs. We'll leave details on this for you to puzzle out.

One tip. Use two \$00 for END values at the end of your note file. That way, should you have an error in your list, you will still stop, catching the second END value.

Where to from here? We have thrown in a quick tester called the TIMBRE TESTER that will get you started in experimenting with different "voices" for your Apple. To use the TIMBRE TESTER, just put a number series into TIMBFLE and the number of numbers into TFLEN. You can get the magic numbers by trial and error, from a venture into Fourier Series (gulp!), or from full-fledged duty cycling experiments.

TIMBRE TESTER works by generating a waveform with many possible zero crossings. As you change the number of zero crossings and the spacing between them, the harmonic content of the note changes, giving you different "voicing" for your Apple.

As examples, a waveform that has very strong fourth, fifth, and sixth harmonics, with a very weak fundamental, second, and third, will sound as a three note major triad chord. Other pleasant two note effects include a strong second and third, third and fourth, fourth and fifth, second and fifth, and third and fifth harmonics. A note with no low harmonics except for the fundamental will voice as a pure and flute-like sinewave.

You can get these harmonics the way you want them, either by trial and error, or else by fancy math.

With duty cycling, you use lots of very high frequency cycles, set up so that the average speaker cone position matches the waveform you are trying to generate. You can easily get pure sinewaves, variable volume, and even exceptionally good human voice synthesis with fancy enough duty cycling.

Each value in TIMBFLE specs the delay time in microseconds, multiplied by five, between cone whappings. For a "fat" sound, you whap the cone many times per frequency cycle. As a fine point, knock two off each VOICE5 value, except for the last one. Knock four off it. Why?

The TIMBRE TESTER can easily give you string and woodwind-style tones, flutelike sinewaves, bells, two notes at once, three notes at once, "noisy" sounds, and even voice. All it takes is the right numbers in the right order.

Finding them is half the fun.

**MIND BENDERS**

- Extend TARZAN by entering the “hard parts” that I left out.
- Write your own songs for SONGPLY.
- Modify SONGPLY so you can control the tempo from a game paddle. Hint: Put the tempo into the Y register.
- Examine the exact timing involved in REDTONE. What effects do slight variations from “perfect” loop timing have?
- Show why LOCKX is not needed and how to replace it.
- Play “Applesoft” by using \$D000 as NOTEFL. Why are the results no longer equally tempered?
- Modify REDTONE for a string voice with an 8:1 duty cycle.
- Show a two byte change to SONGPLY that lets you edit by playing one note at a time.
- Use the TIMBRE TESTER to produce a pure sinewave, and then two notes at once. Then, ring a bell.
- Some poor attempts at duty cycling may buzz or whine. Why? How can you eliminate this?

**PROGRAM RM-5  
MUSICAL SONGS**

----- NEXT OBJECT FILE NAME IS MUSICAL SONGS

6900:           3           ORG \$6900           ; PUT MODULE #5 AT \$6900

```

6900:           5 ; *****
6900:           6 ; *
6900:           7 ; *           -< MUSICAL SONGS >-           *
6900:           8 ; *           ( MODIFIED RED BOOK TONES )           *
6900:           9 ; *           VERSION 1.0 ($6900-$6B3A)           *
6900:           10 ; *           5-24-83           *
6900:           11 ; *           .....*
6900:           12 ; *           COPYRIGHT C 1983 BY           *
6900:           13 ; *           DON LANCASTER AND SYNERGETICS           *
6900:           14 ; *           BOX 1300, THATCHER AZ., 85552           *
6900:           15 ; *           ALL COMMERCIAL RIGHTS RESERVED           *
6900:           16 ; *           *****
6900:           17 ;
6900:           18 ;
6900:           19 ;
6900:           20 ;
6900:           21 ;
6900:           22 ;
6900:           23 ;

```

6900:           25 ;           \*\*\* WHAT IT DOES \*\*\*

```

6900:           27 ;   THIS MODULE SHOWS YOU HOW TO USE THE MODIFIED
6900:           28 ;   RED BOOK TONE SUBROUTINE TO PLAY MUSICAL SONGS.
6900:           29 ;
6900:           30 ;   THERE IS ALSO A TIMBER TESTER FOR EVALUATION
6900:           31 ;   OF SPECIAL APPLE VOICES AND SOUND EFFECTS.

```

6900:           33 ;           \*\*\* HOW TO USE IT \*\*\*

```

6900:           35 ;   TO PLAY A SINGLE NOTE:
6900:           36 ;   PUT YOUR PITCH IN PITCH5 AT $6B3A (27450).
6900:           37 ;   PUT THE DURATION IN DURAT5 AT $6B37 (27447).
6900:           38 ;   THEN JSR REDTONE AT $6B00 (27392).

```

```

6900:           40 ;   TO PLAY YOUR OWN SONG:
6900:           41 ;   PUT THE STARTING ADDRESS OF YOUR SONG INTO
6900:           42 ;   SONGLOC AND SONGLOC+1 AT $6944 AND $6945.
6900:           43 ;   THEN JSR SONGPLY AT $6910. APPLESLOTH
6900:           44 ;   EQUIVALENTS ARE 26948, 26949, AND 26896.

```

```

6900:           46 ;   TO PLAY TARZAN:
6900:           47 ;   DO A JSR $6900 OR CALL 26880.

```

## PROGRAM RM-5, CONT'D . . .

```
6900:          50 ;          *** GOTCHAS ***

6900:          52 ;    A CHANGE OF TEMPO PRESENTLY NEEDS REASSEMBLY.
6900:          53 ;    REDTONE IS LIMITED TO "WOODWIND" SQUARE WAVES.

6900:          55 ;          *** ENHANCEMENTS ***

6900:          57 ;    THIS SOURCE CODE ALSO SHOWS YOU HOW TO COMPOSE
6900:          58 ;    YOUR OWN SONGS IN THE EQUALLY TEMPERED MUSICAL
6900:          59 ;    SCALE BY USING LABELS THAT SIMPLIFY NOTE ENTRY.
6900:          60 ;

6900:          62 ;          *** RANDOM COMMENTS ***

6900:          64 ;    THIS IS "MIDDLEWEIGHT" CODE INTENDED TO SHOW
6900:          65 ;    PROGRAMMING SKILLS AND TECHNIQUES.  FANCIER
6900:          66 ;    METHODS SHOULD BE USED FOR COMMERCIAL PROGRAMS
6900:          67 ;    OR FOR SERIOUS MUSICAL COMPOSITION.
6900:          68 ;

6900:          70 ;          *** HOOKS ***

FC58:          72 HOME    EQU  $FC58    ; CLEAR TEXT SCREEN AND HOME CURSOR
FB2F:          73 INIT    EQU  $FB2F    ; INITIALIZE TEXT SCREEN
C010:          74 KBDSTR  EQU  $C010    ; KEYBOARD STROBE
C000:          75 IOADR   EQU  $C000    ; KEYBOARD INPUT LOCATION
C030:          76 SPKR    EQU  $C030    ; SPEAKER CLICK OUTPUT
C020:          77 TAPEOUT EQU  $C020    ; CASSETTE TAPE OUT (TONE ECHO)
FCA8:          78 WAIT    EQU  $FCA8    ; MONITOR TIME DELAY

00EF:          80 NOTEP   EQU  $EF      ; NOTE POINTER PAIR FOR SONGLPLY
```

## PROGRAM RM-5, CONT'D . . .

```

6900:      83 ;          *** CONSTANTS ***

6900:      85 ;          PITCH LABELS USED FOR SONG COMPOSITION
6900:      86 ;
6900:      87 ;          FOR BEST SOUND, ALWAYS USE THE NOTE
6900:      88 ;          VALUES NEAREST THE TOP OF THIS LIST.

00E8:      90 A1      EQU 232      ; NOTE A BELOW MIDDLE C

00DB:      92 A1S     EQU 219      ; A#
00DB:      93 B1F     EQU 219      ; Bb
00CF:      94 B1      EQU 207      ; B
00C3:      95 C1      EQU 195      ; C
00B8:      96 C1S     EQU 184      ; C#
00B8:      97 D1F     EQU 184      ; Db
00AE:      98 D1      EQU 174      ; D
00A4:      99 D1S     EQU 164      ; D#
00A4:     100 E1F     EQU 164      ; Eb
009B:     101 E1      EQU 155      ; E
0092:     102 F1      EQU 146      ; F
008A:     103 F1S     EQU 138      ; F#
008A:     104 G1F     EQU 138      ; Gb
0082:     105 G1      EQU 130      ; G
007B:     106 G1S     EQU 123      ; G#
007B:     107 A1F     EQU 123      ; Ab

0074:     109 A2      EQU 116      ; NOTE A ABOVE MIDDLE C

006E:     111 A2S     EQU 110      ; A#
006E:     112 B2F     EQU 110      ; Bb
0067:     113 B2      EQU 103      ; B
0062:     114 C2      EQU 98       ; C
005C:     115 C2S     EQU 92       ; C#
005C:     116 D2F     EQU 92       ; Db
0057:     117 D2      EQU 87       ; D
0052:     118 D2S     EQU 82       ; D#
0052:     119 E2F     EQU 82       ; Eb
004E:     120 E2      EQU 78       ; E
0049:     121 F2      EQU 73       ; F
0045:     122 F2S     EQU 69       ; F#
0045:     123 G2F     EQU 69       ; Gb
0041:     124 G2      EQU 65       ; G
003D:     125 G2S     EQU 61       ; G#
003D:     126 A2F     EQU 61       ; Ab

003A:     128 A3      EQU 58       ; SECOND A ABOVE MIDDLE C

00FF:     130 R       EQU $FF      ; SILENT OR REST
0000:     131 END     EQU $00      ; END OF SONG (USE TWICE!)

```



## PROGRAM RM-5, CONT'D . . .

```
6900:      134 ;      DURATION LABELS USED FOR SONG COMPOSITION

6900:      136 ;      A REPEAT ASSEMBLY PASS IS NEEDED AT
6900:      137 ;      PRESENT FOR EACH CHANGE IN TEMPO.

0009:      139 TEMPO  EQU  $09      ; MASTER TEMPO CONTROL ($OF MAXIMUM!)
0080:      140 MULT   EQU  $80      ; TEMPO MULTIPLIER (00=X1 $80=X2 $40=X4
0048:      141 PAUSE  EQU  $48      ; INTERNOTE PAUSE TIME

0009:      143 S      EQU  TEMPO*1  ; SIXTEENTH NOTE
000D:      144 DS     EQU  S/2+S    ; DOTTED SIXTEENTH
0012:      145 E      EQU  TEMPO*2  ; EIGHTH NOTE
001B:      146 DE     EQU  TEMPO*3  ; DOTTED EIGHTH
0024:      147 Q      EQU  TEMPO*4  ; QUARTER NOTE
0036:      148 DQ     EQU  TEMPO*6  ; DOTTED QUARTER
0048:      149 H      EQU  TEMPO*8  ; HALF NOTE
006C:      150 DH     EQU  TEMPO*12 ; DOTTED HALF NOTE
0090:      151 W      EQU  TEMPO*16 ; WHOLE NOTE
```

## PROGRAM RM-5, CONT'D . . .

```

6900:      155 ;      *** MUSICAL SONGS ***
6900:      156 ;
6900:      157 ;      THIS SUBROUTINE USES REDTONE TO PLAY THE
6900:      158 ;      SONG WHOSE STARTING ADDRESS IS IN SONGLOC.

6900:20 2F FB 160 TAR      JSR INIT      ; INITIALIZE TEXT SCREEN
6903:20 58 FC 161          JSR HOME      ; AND CLEAR IT

6906:A9 46      163          LDA #>TARZAN ; TO PLAY TARZAN ONLY
6908:8D 44 69 164          STA SONGLOC ;
690B:A9 69      165          LDA #<TARZAN ;
690D:8D 45 69 166          STA SONGLOC+1 ;

6910:AD 44 69 168 SONGPLY LDA SONGLOC ; MOVE SONG ADDRESS TO POINTER
6913:85 EF      169          STA NOTEP ;
6915:AD 45 69 170          LDA SONGLOC+1 ; POSITION THEN PAGE AS USUAL
6918:85 F0      171          STA NOTEP+1 ;

691A:A0 00      173          LDY #$00      ; FOR PURE INDIRECT
691C:A9 80      174          LDA #MULT     ; SET DURATION MULTIPLIER
691E:8D 39 6B 175          STA DURMUL5 ; AND POKE TO REDTONE

6921:B1 EF      177 MORE5   LDA (NOTEP),Y ; GET PITCH VALUE
6923:F0 1E      178          BEQ DONE5   ; EXIT IF END
6925:8D 3A 6B 179          STA PITCH5   ; POKE PITCH
6928:E6 EF      180          INC NOTEP   ; GO TO NEXT FILE VALUE
692A:D0 02      181          BNE NOCY5   ; PAGE OVERFLOW?
692C:E6 F0      182          INC NOTEP+1 ; YES
692E:B1 EF      183 NOCY5   LDA (NOTEP),Y ; GET DURATION VALUE
6930:8D 37 6B 184          STA DURAT5   ; STASH DURATION VALUE
6933:20 00 6B 185          JSR REDTONE ; PLAY THE NOTE
6936:A9 48      186          LDA #PAUSE   ; GET INTERNOTE DELAY
6938:20 A8 FC 187          JSR WAIT     ; AND DELAY
693B:E6 EF      188          INC NOTEP   ; GO TO NEXT FILE VALUE
693D:D0 E2      189          BNE MORE5   ; PAGE OVERFLOW?
693F:E6 F0      190          INC NOTEP+1 ; YES
6941:D0 DE      191          BNE MORE5   ; ALWAYS (WELL, ALMOST!)

6943:60      193 DONE5   RTS      ; END OF SONG

```

## PROGRAM RM-5, CONT'D . . .

6944: 196 ; \*\*\* SONG POINTER STASE \*\*\*

6944:46 69 198 SONGLOC DFB >TARZAN,<TARZAN

6946: 200 ; \*\*\* SONG FILE \*\*\*

6946: 202 ; EACH NOTE IS ENTERED, PITCH FIRST AND

6946: 203 ; DURATION SECOND USING LABELS AS SHOWN.

6946: 204 ;

6946:74	48	74	206	TARZAN	DFB	A2,H,A2,H,G1,Q,F1S,Q,F1S,H
6949:48	82	24				
694C:8A	24	8A				
694F:48						
6950:92	24	8A	207		DFB	F1,Q,F1S,Q,F1S,W,R,H
6953:24	8A	90				
6956:FF	48					
6958:92	24	8A	208		DFB	F1,Q,F1S,Q,F1S,H,F1,Q,F1S,Q
695B:24	8A	48				
695E:92	24	8A				
6961:24						
6962:74	48	8A	209		DFB	A2,H,F1S,DQ,A2,E,G1,W,E1,DH,R,Q
6965:36	74	12				
6968:82	90	9B				
696B:6C	FF	24				
696E:9B	48	A4	210		DFB	E1,H,D1S,Q,E1,Q,E1,H
6971:24	9B	24				
6974:9B	48					
6976:A4	24	9B	211		DFB	D1S,Q,E1,Q,A2,W,R,H
6979:24	74	90				
697C:FF	48					
697E:8A	24	9B	212		DFB	F1S,Q,E1,Q,F1S,Q,A2,DH
6981:24	8A	24				
6984:74	6C					
6986:67	6C	67	213		DFB	B2,DH,B2,Q,E1,W,R,H
6989:24	9B	90				
698C:FF	48					
698E:74	48	74	214		DFB	A2,H,A2,H,G1,Q,F1S,Q,F1S,H
6991:48	82	24				
6994:8A	24	8A				
6997:48						
6998:92	24	8A	215		DFB	F1,Q,F1S,Q,F1S,W,R,H
699B:24	8A	90				
699E:FF	48					

## PROGRAM RM-5, CONT'D . . .

69A0:92	24	8A	218	DFB	F1,Q,F1S,Q,F1S,H,F1,Q,G1,Q
69A3:24	8A	48			
69A6:92	24	82			
69A9:24					
69AA:82	24	8A	219	DFB	G1,Q,F1S,Q,E1,DQ,C2S,E,E1,DH,D1,H
69AD:24	9B	36			
69B0:5C	12	9B			
69B3:6C	AE	48			
69B6:FF	24	AE	220	DFB	R,Q,D1,Q,D1,H,C1S,Q,D1,Q
69B9:24	AE	48			
69BC:B8	24	AE			
69BF:24					
69C0:92	48	9B	221	DFB	F1,H,E1,Q,D1,Q,D2,W,R,Q
69C3:24	AE	24			
69C6:57	90	FF			
69C9:24					
69CA:92	24	9B	222	DFB	F1,Q,E1,Q,F1S,Q,A2,E,R,E,D1,Q
69CD:24	8A	24			
69D0:74	12	FF			
69D3:12	AE	24			
69D6:9B	24	8A	223	DFB	E1,Q,F1S,Q,A2,E,R,E
69D9:24	74	12			
69DC:FF	12				
69DE:E8	24	CF	224	DFB	A1,Q,B1,Q,F1S,Q,E1,W,D1,Q
69E1:24	8A	24			
69E4:9B	90	AE			
69E7:24					
69E8:00	00		225	DFB	END,END

## PROGRAM RM-5, CONT'D . . .

```

69EA:          228 ;          *** TIMBRE TESTER ***
69EA:          229 ;
69EA:          230 ;          THIS ROUTINE LETS YOU EVALUATE SPECIAL VOICES,
69EA:          231 ;          DUTY CYCLING, MULTI-TONES AND OTHER EFFECTS.
69EA:          232 ;
69EA:          233 ;          TO USE, LOAD TIMBFLE WITH THE DELAY VALUES
69EA:          234 ;          BETWEEN ZERO CROSSINGS. LOAD TFLENGTH WITH
69EA:          235 ;          THE NUMBER OF ZERO CROSSINGS PER FUNDAMENTAL
69EA:          236 ;          NOTE CYCLE.
69EA:          237 ;
69EA:          238 ;          TO RUN:
69EA:          239 ;
69EA:          240 ;          JSR $6AC0 FROM MACHINE LANGUAGE
69EA:          241 ;          CALL 27328 FROM APPLESLOTH.
69EA:          242 ;
69EA:          243 ;          EXIT ON ANY KEY PRESSED.

6AC0:          245          ORG TAR+$01C0 ; LEAVE ROOM FOR SONG FILES

6AC0:2C 10 C0 247 TIMBRE BIT KBDSTR ; RESET KEYBOARD
6AC3:AE DE 6A 248 RESCAN5 LDX TFLENGTH ; START NEW SCAN
6AC6:CA          249 NEXT5 DEX ; NEXT VALUE
6AC7:30 FA          250          BMI RESCAN5 ; RESET IF COMPLETE
6AC9:BC DF 6A 251          LDY TIMBFLE,X ; GET DELAY VALUE
6ACC:88          252 LOOP5 DEY ; DELAY 5N+1 CYCLES
6ACD:D0 FD          253          BNE LOOP5 ; STALL FOR TIME
6ACF:2C 30 C0 254          BIT SPKR ; WHAP SPEAKER
6AD2:2C 20 C0 255          BIT TAPEOUT ; WHAP CASSETTE OUTPUT
6AD5:2C 00 C0 256          BIT IOADR ; KEYPRESSED?
6AD8:10 EC          257          BPL NEXT5 ; REPEAT IF NO KP
6ADA:2C 10 C0 258          BIT KBDSTR ; RESET KEYSTROBE
6ADD:60          259          RTS ; AND EXIT

6ADE:          261 ;          *** TIMBRE DELAY VALUES ***

6ADE:08          263 TFLENGTH DFB $08 ; NUMBER OF CROSSINGS IN TIMBFLE

6ADF:60 6A 6A 265 TIMBFLE DFB          $60,$6A,$6A,$27
6AE2:27
6AE3:27 6A 6A 266          DFB          $27,$6A,$6A,$5E
6AE6:5E

```

## PROGRAM RM-5, CONT'D . . .

```

6AE7:          269 ;      *** MODIFIED RED BOOK TONE SUBROUTINE ***

6AE7:          271 ;      A JSR TO REDTONE PLAYS A SINGLE NOTE.
6AE7:          272 ;
6AE7:          273 ;      THE PITCH MUST BE PREPLACED IN PITCH5
6AE7:          274 ;      DURATION MUST BE PREPLACED IN DURAT5.
6AE7:          275 ;
6AE7:          276 ;      A PITCH5 VALUE OF $FF IS SILENT.

6B00:          278          ORG  TAR+$0200 ; LEAVE ROOM FOR TIMBRE FILES

6B00:48        280 REDTONE PHA          ; SAVE REGISTERS
6B01:98        281          TYA          ;
6B02:48        282          PHA          ;
6B03:8A        283          TXA          ;
6B04:48        284          PHA          ;
6B05:AD 37 6B 285          LDA  DURAT5  ; MOVE DURATION VALUE TO
6B08:8D 38 6B 286          STA  DURCNT5 ; COUNTABLE LOCATION

6B0B:A0 00     288          LDY  #$00   ; INIT FAST DURATION COUNTER
6B0D:98        289          TYA          ; INIT DURATION MULTIPLIER

6B0E:AE 3A 6B 291 WHAP   LDX  PITCH5 ; GET PITCH VALUE
6B11:E0 FF     292          CPX  #$FF   ; IS IT SILENT?
6B13:F0 19     293          BEQ  LOCKX  ; YES, KEEP IT SILENT
6B15:2C 30 C0 294          BIT  SPKR   ; WHAP SPEAKER
6B18:2C 20 C0 295          BIT  TAPEOUT ; AND ECHO TO CASSETTE OUTPUT
6B1B:88        296 NOWHAP DEY          ; DECREMENT FAST DURATION COUNT
6B1C:D0 0B     297          BNE  NOC5   ; IF NO BORROW
6B1E:18        298          CLC          ;
6B1F:6D 39 6B 299          ADC  DURMUL5 ; DURATION MULTIPLIER
6B22:D0 05     300          BNE  NOC5   ; IGNORE ALL BUT ZERO RESULTS
6B24:CE 38 6B 301          DEC  DURCNT5 ; DECREMENT SLOW DURATION
6B27:F0 08     302          BEQ  EXIT5  ; IF FINISHED
6B29:CA        303 NOC5   DEX          ; DECREMENT PITCH VALUE
6B2A:D0 EF     304          BNE  NOWHAP ; PITCH NOT DONE
6B2C:F0 E0     305          BEQ  WHAP   ; PITCH DONE, ALWAYS TAKEN

6B2E:E8        307 LOCKX  INX          ; TRAP X TO $FF
6B2F:F0 EA     308          BEQ  NOWHAP ; ALWAYS TAKEN

6B31:68        310 EXIT5  PLA          ; RESTORE REGISTERS
6B32:AA        311          TAX          ;
6B33:68        312          PLA          ;
6B34:A8        313          TAY          ;
6B35:68        314          PLA          ;
6B36:60        315          RTS          ; AND EXIT

```

PROGRAM RM-5, CONT'D . . .

```
6B37:          318 ;          *** REDTONE STASH ***
6B37:72        320 DURAT5  DFB  $72      ; DURATION GOES HERE
6B38:72        321 DURCNT5 DFB  $72      ; GETS COUNTED HERE
6B39:80        322 DURMUL5 DFB  $80      ; DURATION MULTIPLIER
6B3A:72        323 PITCH5  DFB  $72      ; PITCH GOES HERE
```

\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS

## OPTION PICKER

**a general and flexible way to  
handle menu selections and in-  
program jumps**

Just about any larger program eventually gets to a point where it has to jump six ways from Sunday. These may involve internal jumps, such as when an adventure decides it has to check to be sure the giant armadillo is awake. Or, they might involve user input, such as a menu selection, the “T” for trace command of a monitor, or the “[S]” save command of a word processor.

A code module that lets a program go to one of many possible tasks is called an *option picker* . . .

### **OPTION PICKER—**

**A code module that lets a program  
continue by jumping to a selected  
one of many possible tasks.**

Now, option picking doesn’t sound like a very big deal. The trick is to come up with one single option picker that you can adapt to any program you want to, while keeping things as short and as flexible as possible.




the code for each and every application. This way, you know your code works ahead of time. Any problems are likely to be file problems that are easily spotted and more easily fixed.

Let's check into the most general and often the "best" way to pick one of many options. To do this, get a character from a program or a keyboard. Then, if needed, change lowercase to uppercase. Next, filter your character by looking into a file to find a character match. If there's no match, process the error and try again. If you do find a match, go to a second file and grab an address to go to. Then, jump to that address.

Something like this . . .

### HOW TO PICK AN OPTION:



There are several distinct parts to a good and flexible option picker. First, you normally will want the same response for a capital letter as for a small one, say for "A" and "a." If you do, you will need case *changer* code. If you are allowing for meaningful, rather than ordered, inputs, then you will also need an *option filter* that converts the selections into a binary file access number.

Then there are possible errors. Sometimes a few *legal* and *expected* responses may all want to go to the same option. We can call that jump an *inclusive trap*. The simplest way to handle inclusive traps is

just to repeat the same address in the address file as often as needed. There are ways, of course, to save a byte or two on this, but you end up with custom code if you try this. We will use an error message of "PLEASE TRY ANOTHER LETTER" to show this when it happens in the upcoming GILA demo.

Other times, the input will not match any legal selection. What you have to do here is go get another input since the one you have is no good. You can call this an *exclusive trap*. Exclusive traps should go and try and get another response.

You must always inform the user that you don't like his invalid selection. The trick here is to do it as subtly and gently as possible. More often than not, a brief screen flash or a single speaker click is all you will need. We will use a message of "THAT'S NO LETTER, YOU TURKEY!" in the demo. Naturally, such harshness must be used with discretion in commercial programs.

Should the program, rather than the user, be making the option selection, you will end up in deep trouble if the computer decides to do something it is not set up to do. In *Zork*, machine errors are trapped with a "ZORK INTERNAL ERROR" message. Chances are overwhelming that you have not and will not get one of these *Zork* messages.

Unless you play *Zork* the way I do.

Needless to say, machine errors are never supposed to happen. When and if one does, though, be sure to inform the user that he has just been done in through no fault of his own. It may be a good idea to encourage the user to "close the loop" and contact you personally when this happens.

Not *if*, but *when*.

A final part of the option picker has to actually do a jump or a gosub to the selected option. You have many choices here. Building the jumps into the code as we did above is obviously bad, since the code is no longer general. You can also self-modify your code by having a JMP command whose address you pre-change to the address you want to jump to. This is risky and does not work in ROM, but is cute and compact. You can also force a JSR the same way.

The JMP indirect command is another possibility. Here, you put your address somewhere on page zero, say \$06 low and \$07 high. Then a JMP (\$06) does an indirect jump to your intended address. For a forced subroutine, just do a JSR to an indirect JMP.

But, remember that the original 6502 JMP indirect has a bug in it that prevents you from using it properly on either of the top two bytes of any page. If you relocate your code, or do not watch very carefully where your JMP indirects are, this bug may bomb your code. Page zero real estate is valuable enough that you should go out of your way to avoid using it whenever there are reasonable alternatives.

By the way, certain copy protection fanatics intentionally put their JMP indirects in the "wrong" locations, hoping you miss the turn. The jumped-to locations end up on the bottom of the *same* page, rather than the expected bottom of the *next* page this way. Of course, such childish and inane stunts just add to the fun and challenge of cracking the "uncrackable." Besides, they will bomb on an Apple upgraded to a 65C02. Or on a IIc.

Har har.

Anyway, the way I like to do a jump to an option is with a scheme

called the *forced subroutine return* method. This method is used in the Apple system monitor, so it is not new. But it is super powerful and elegant.

Remember that a subroutine return or RTS checks into the stack and gets the top stack location. It uses this location for the position on the page it is to return to. Then, it goes one deeper into the stack to get the page location. Given the position and the page, the RTS then jumps to this location *plus one*.

Normally, of course, the RTS returns to the code that called it. Now to get sneaky. Take the page address of your option and shove it on the stack with a PHA. Then, take the option position address *minus one* and shove it on the stack with a second PHA. Now, RTS. What happens?

You “return” to the address of your selected option!

Note that two pushes (by you) and two pulls (by the RTS) leave the stack the way it was before you started. So you are still in the same “level” of your code both before and after you force the fake subroutine return. Note also that no page zero locations are committed.

For an earlier and different example of using forced subroutine returns, check back into IMPRINT of Ripoff Module 2.

Let’s sum up the parts of our option picker . . .

**CASE CHANGER—**

Code that forces lowercase letters into their uppercase equivalents.

**OPTION FILTER—**

Code that finds a match between user inputs and a binary value.

**INCLUSIVE TRAP—**

Several user selections that all divert to the same option.

**EXCLUSIVE TRAP—**

Code that finds “illegal” user inputs and suitably handles this type of error.

**FORCED SUBROUTINE RETURN—**

A JMP indirect that is faked by pushing an address pair onto the stack and then doing an RTS.

Summing up, while there are lots of ways to pick options, we will use a general and powerful file based method that is easy to use and easy to change. It is best suited for six or more unordered choices. The code is very efficient when many different selections are made.

To pick an option, you first change the case of lowercase letters, so that either a capital “A” or a lowercase “a” gets the same response. Then you look for a match in a character file. Finding the match generates a binary number useful as an address pointer.

Should a match be found, the binary number is doubled and used to access an address pair in an address file. This address pair is forced

onto the stack and is then followed by an RTS, doing a jump to the selected option.

Two crucial reminders . . .

**When “force feeding” a stack—  
ALWAYS push the page address on first,  
followed by the position address.  
ALWAYS use an address ONE LESS than  
your intended return point.**

The sneaky way to automatically remove one from any address is to let your assembler’s operand arithmetic handle the chore for you. Thus, instead of a label of TASKA, use TASKA-1 when defining addresses in your address file. The DW command is one good way to handle 2-byte pairs. DW automatically rearranges these pairs into their “position-page” format for you.


Don’t forget these two crucial details: The page goes on the stack first, and RTS ends up one beyond the stack address.

Several matches can point to the same address pair by repeating the address pair when and where needed in the address file. We have seen how this is called an inclusive trap.

Should no match be found, an exclusive trap tries for a new input or generates an error message, informing the user as this happens.

The option picking subroutine is called OPICK. Its flowchart looks like this . . .

**OPICK FLOWCHART:**



Some parts of OPICK might not be needed for all uses. For instance, you can delete getting a key if the machine itself is to provide the option selection.

Delete the case changer if you want something different to happen for a capital letter than for a lowercase one. Sometimes, your options will not even be in ASCII. They might be a binary selection. If so, lowercase is meaningless.

The option filter can be deleted if you are certain your option selections are always ordered binary numbers. This is OK for internal use, but, as we've seen, is a poor and unfriendly choice where users are involved.

And, don't use such heavy code for trivial choices. A simple (Y/N) checker can be done much faster with many fewer bytes. For over six choices, the option filter is the better way to go. The more the choices and the more wildly they are arranged, the better the method gets.

The FIXCASE case changer works by testing for a lowercase ASCII letter. If it gets one of these, then \$20 is subtracted as needed to get uppercase. For instance, a lowercase "a" is an ASCII \$E1. Subtract \$20 to get \$C1, the ASCII uppercase "A." It pays to test for "z" as well as "a" so that any punctuation above ASCII \$FA does not get changed. We've shown high ASCII here, as you get off the Apple keyboard before resetting the keystroke.

Any match character can go in any order, except that the position of the address in the address table must be exactly twice the position of the match character in the match file. All this says is that the match must line up with where you want the match to go to. The doubling is needed for the 2-byte absolute address pairs and is handled with an ASL multiplier.

The matches in the match file can go in any order. The obvious and cleanest arrangement is to put the selections in logical user input order. Another way is to put the addresses in the order they appear in the program. Still another way is to put the often used matches first, in an attempt to gain a slight speedup. Just be sure that the match and the match address are aligned to each other.

We have put the match values in alphabetical order. Once again, though, you can put any mix of numbers, letters, and control characters in any order, skipping around anywhere you like.

As we have seen, the cleanest way to handle inclusive traps is to repeat the address pair as often as needed in your address file.

We used an inverse title for this demo, like we did with IMPRINT and FLPRINT. These titles are quick and dirty to do, but they are usually far too garish to use in a commercial program. A single inverse line cuts the tops of uppercase letters and random tops and bottoms of lowercase. The obvious cure for this of using three inverse lines to form a box usually is too "loud" for the rest of the screen.

So, do as I say, not as I do . . .

**AVOID using inverse text headers and titles on commercial programs.**

**These are too garish and imperfect to give you acceptable results.**

You have a choice of using your options as subroutines or else as same-level jumps. If, as we did in GILA, you JSR to OPICK and then force-return to your option, an RTS at the end of the option returns you to the code that is calling OPICK.

On the other hand, you could JMP to OPICK and then force-return to your option. Here, a JMP at the end of the option is needed to return you to a calling code.

In one method, the options are subroutines. In the other, they are at the same level as the code that calls OPICK.

To adapt OPICK to your own needs, just change the MAXMATCH number to equal the total number of options, change the MATCHFL file to hold the characters you are matching against, and change the JMPFLE to hold the addresses you want to jump to. A reassembly, of course, will be needed. As usual, labels that name each option you are to jump to greatly simplify and automate the process of building this file. Makes it fun even.

Time for . . .

### **A Demo**

Normally, your option picker will jump to lots of wildly different types of code in your main program. To keep DEMO6 simple, we will still jump to lots of different points in the main program, but the action at each option point will be rather simple and sort of redundant. Now, there probably are better ways to write a program that does what this demo does, but, remember that we are trying to show the *method* of using an option picker to go many places in a larger program.

DEMO6 is our demo, and what it does is generate the name of a town in exchange for a user input that matches the first letter of that town. Once you have recovered from the initial excitement of such a stupendous program, look carefully to see how the options each go to a selected code module, and how the inclusive and exclusive traps are working. Note how both control commands and letter inputs are handled. See how the ESC key exits the program for you.

Incidentally, we've used our own key getter, rather than GETKEY. It's tricky to handle escape commands with GETKEY, and GETKEY gives slightly different results on a II versus a IIe. The prompt gets entered by using IMPRINT to print a prompt, followed by a back-space, followed by the double zero exit.

DEMO6 has borrowed the IMPRINT code from Ripoff Module 2, so be sure that either this code, a copy of it, or else a copy of THE WHOLE BALL OF WAX is present in the machine.

**MIND BENDERS**

- Rework the demo to use your own towns in your own local area.
- Change the demo to other topics, such as autos, aircraft, animals, vegetables, or nurflongs.
- What other uses are there for the forced subroutine method?
- How long does the option picker take to process an option?
- Show how to use your options as same level code, rather than as subroutines.
- What other user prompting can be used in place of the time delay?
- Explain away those two PLAs in the exit code. Why are they used?
- Try to BRUN OPTION PICKER directly from your disk, and [ESC] will not exit you from your program. Why?
- Display a different LORES or HIRES picture for each selection, along with suitable sound.



**PROGRAM RM-6  
OPTION PICKER**

----- NEXT OBJECT FILE NAME IS OPTION PICKER

6C00:           3            ORG \$6C00           ; PUT MODULE #6 AT \$6C00

```

6C00:           5 ; *****
6C00:           6 ; *
6C00:           7 ; *                   -< OPTION PICKER >-
6C00:           8 ; *
6C00:           9 ; *   ( JUMPING SIX WAYS FROM SUNDAY )
6C00:          10 ; *
6C00:          11 ; *           VERSION 1.0 ($6C00-$6EDD)
6C00:          12 ; *
6C00:          13 ; *                   5-24-83
6C00:          14 ; * .....
6C00:          15 ; *
6C00:          16 ; *           COPYRIGHT C 1983 BY
6C00:          17 ; *
6C00:          18 ; *   DON LANCASTER AND SYNERGETICS
6C00:          19 ; *   BOX 1300, THATCHER AZ., 85552
6C00:          20 ; *
6C00:          21 ; *   ALL COMMERCIAL RIGHTS RESERVED
6C00:          22 ; *
6C00:          23 ; *****

```

6C00:           25 ;           \*\*\* WHAT IT DOES \*\*\*

```

6C00:           27 ;   THIS MODULE SHOWS YOU HOW TO JUMP TO ONE OF MANY
6C00:           28 ;   POSSIBLE POINTS TO CONTINUE RUNNING A PROGRAM.
6C00:           29 ;

```

6C00:           31 ;           \*\*\* HOW TO USE IT \*\*\*

```

6C00:           33 ;   TO USE THE OPTION PICKER:
6C00:           34 ;
6C00:           35 ;   REASSEMBLE WITH YOUR NUMBER OF MATCHES IN MATCHN,
6C00:           36 ;   YOUR MATCHES IN MATCHFL AND YOUR JUMP
6C00:           37 ;   VECTORS MINUS ONE IN JMPFL. THEN JSR
6C00:           38 ;   OPICK AT $6E45 (28229).

```

```

6C00:           40 ;   TO RUN THE GILA TOWNS DEMO:
6C00:           41 ;
6C00:           42 ;   JSR GILA AT $6C00 OR CALL 27648.

```

## PROGRAM RM-6, CONT'D . . .

```
6C00:      45 ;          *** GOTCHAS ***

6C00:      47 ; THE IMPRINT SUBROUTINE MUST BE PRESENT IN THE
6C00:      48 ; MACHINE. PRELOAD "IMPRINT" OR "THE WHOLE BALL
6C00:      49 ; OF WAX" TO DO THIS.
6C00:      50 ;
6C00:      51 ; JUMP VECTORS MUST BE IN THE USUAL "POSITION-
6C00:      52 ; PAGE" ORDER. THE ORDER IN MATCHFL MUST EQUAL
6C00:      53 ; THE ORDER IN TASKFL.
6C00:      54 ; JUMP VECTORS MUST BE ONE LESS THAN
6C00:      55 ; THEIR ACTUAL RETURN POINTS!

6C00:      57 ;          *** ENHANCEMENTS ***

6C00:      59 ; MATCHED CHARACTERS CAN BE IN ANY ORDER AND MAY
6C00:      60 ; INCLUDE CONTROL CHARACTERS.
6C00:      61 ;
6C00:      62 ; INCLUSIVE TRAPS ARE DONE BY REPEATING THE TASKFL
6C00:      63 ; JUMP VECTORS AS OFTEN AS NEEDED.
6C00:      64 ;

6C00:      66 ;          *** RANDOM COMMENTS ***

6C00:      68 ; THERE ARE CERTAINLY BETTER WAYS TO HANDLE THE
6C00:      69 ; GILA TOWNS DEMO THAN THIS. IN REAL LIFE, EACH
6C00:      70 ; "TOWN" REPRESENTS A DIFFERENT AND UNIQUE HIGH
6C00:      71 ; LEVEL PROGRAMMING TASK.
6C00:      72 ;
6C00:      73 ; THE DEMO ALSO SHOWS HOW TO CHANGE THE SCROLLING
6C00:      74 ; TEXT WINDOW UNDER PROGRAM CONTROL.
```

## PROGRAM RM-6, CONT'D . . .

```
6C00:          77 ;          *** HOOKS ***

FC58:          79 HOME    EQU  $FC58    ; CLEAR TEXT SCREEN AND HOME CURSOR
FB2F:          80 INIT    EQU  $FB2F    ; INITIALIZE TEXT SCREEN
C000:          81 IOADR   EQU  $C000    ; KEYBOARD INPUT LOCATION
C010:          82 KBDSTRB EQU  $C010    ; KEYBOARD STROBE RESET
FE80:          83 SETINV  EQU  $FE80    ; SET INVERSE SCREEN
FE84:          84 SETNORM EQU  $FE84    ; SET NORMAL SCREEN
C030:          85 SPKR    EQU  $C030    ; SPEAKER CLICK OUTPUT
FCA8:          86 WAIT    EQU  $FCA8    ; MONITOR TIME DELAY

666B:          88 IMPRINT EQU  $666B    ; LINK TO IMPRINT SUBROUTINE

0020:          90 WNDLFT  EQU  $20      ; LEFT SIDE OF SCROLL WINDOW
0021:          91 WNDWTH  EQU  $21      ; WIDTH OF SCROLL WINDOW
0022:          92 WNDTOP  EQU  $22      ; TOP OF SCROLL WINDOW
0023:          93 WNDBTM  EQU  $23      ; BOTTOM OF SCROLL WINDOW
0024:          94 CH      EQU  $24      ; CURSOR HORIZONTAL POSITION
0025:          95 CV      EQU  $25      ; CURSOR VERTICAL POSITION
0033:          96 PROMPT  EQU  $33      ; PROMPT SYMBOL

6C00:          98 ;          *** TEXTFILE COMMANDS ***

0088:          100 B      EQU  $88      ; BACKSPACE
008D:          101 C      EQU  $8D      ; CARRIAGE RETURN
0084:          102 D      EQU  $84      ; DOS ATTENTION
009B:          103 E      EQU  $9B      ; ESCAPE
008A:          104 L      EQU  $8A      ; LINEFEED
0060:          105 P      EQU  $60      ; FLASHING PROMPT
0000:          106 X      EQU  $00      ; END OF MESSAGE
```

## PROGRAM RM-6, CONT'D . . .

```

6C00:          109 ;          *** GILA TOWNS DEMO ***
6C00:          110 ;
6C00:          111 ; THIS PROGRAM EXERCISES THE OPTION
6C00:          112 ; PICKER SUBROUTINE OPICK.
6C00:          113 ;
6C00:          114 ; EACH "TOWN" REPRESENTS A DIFFERENT
6C00:          115 ; HIGH LEVEL PROGRAM TASK.

6C00:20 2F FB 117 GILA JSR INIT ; SET UP TEXT SCREEN
6C03:20 58 FC 118 JSR HOME ; CLEAR SCREEN AND HOME CURSOR
6C06:A9 07 119 LDA #07 ; TAB 7 TO RIGHT
6C08:85 24 120 STA CH ;
6C0A:20 80 FE 121 JSR SETINV ; INVERSE TITLE
6C0D:20 6B 66 122 JSR IMPRINT ; PUT DOWN TITLE
6C10:8A 8A 8A 123 DFB L,L,L
6C13:CF D0 D4 124 ASC "OPTION PICKER DEMO"
6C16:C9 CF CE
6C19:A0 D0 C9
6C1C:C3 CB C5
6C1F:D2 A0 C4
6C22:C5 CD CF
6C25:8D 8D 8D 125 DFB C,C,C,C,X
6C28:8D 00

6C2A:20 84 FE 127 JSR SETNORM ; BACK TO NORMAL TEXT
6C2D:20 6B 66 128 JSR IMPRINT ; PUT DOWN INSTRUCTIONS
6C30:D4 D9 D0 129 ASC "TYPE THE FIRST LETTER TO GET THE"
6C33:C5 A0 D4
6C36:C8 C5 A0
6C39:C6 C9 D2
6C3C:D3 D4 A0
6C3F:CC C5 D4
6C42:D4 C5 D2
6C45:A0 D4 CF
6C48:A0 C7 C5
6C4B:D4 A0 D4
6C4E:C8 C5
6C50:8D 130 DFB C
6C51:C6 D5 CC 131 ASC "FULL NAME OF A GILA VALLEY TOWN:"
6C54:CC A0 CE
6C57:C1 CD C5
6C5A:A0 CF C6
6C5D:A0 C1 A0
6C60:C7 C9 CC
6C63:C1 A0 D6
6C66:C1 CC CC
6C69:C5 D9 A0
6C6C:D4 CF D7
6C6F:CE BA

```

## PROGRAM RM-6, CONT'D . . .

```

6C71:8D 8D 8D 134      DFB      C,C,C,C
6C74:8D
6C75:A0 A0 A0 135      ASC      "      ----> "
6C78:A0 A0 A0
6C7B:A0 A0 AD
6C7E:AD AD BE
6C81:A0
6C82:8D 8D 8D 136      DFB      C,C,C,C,C,C
6C85:8D 8D 8D
6C88:A0 A0 A0 137      ASC      /      (USE "ESC" TO EXIT)/
6C8B:A0 A0 A0
6C8E:A8 D5 D3
6C91:C5 A0 A2
6C94:C5 D3 C3
6C97:A2 A0 D4
6C9A:CF A0 C5
6C9D:D8 C9 D4
6CA0:A9
6CA1:00      138      DFB      X

6CA2:A9 0D      140      LDA      #$0D      ; SET TIGHT WINDOW
6CA4:85 20      141      STA      WNDLFT    ;
6CA6:A9 15      142      LDA      #$15      ;
6CA8:85 21      143      STA      WNDWTH    ;
6CAA:A9 0C      144      LDA      #$0C      ;
6CAC:85 22      145      STA      WNDTOP    ;
6CAE:A9 0F      146      LDA      #$0F      ;
6CB0:85 23      147      STA      WNDBTM    ;
6CB2:20 58 FC  148      JSR      HOME      ; GET IN WINDOW
6CB5:A9 60      149      LDA      #P        ; CHANGE PROMPT
6CB7:85 33      150      STA      PROMPT    ;

6CB9:20 6B 66  152 DOOPT JSR      IMPRINT    ; ADD WINKING CURSOR
6CBC:60 88 00  153      DFB      P,B,X
6CBF:20 44 6E  154      JSR      OPICK     ; GET AND DO OPTIONS AS SUBS

6CC2:A2 0D      156 CONT6 LDX      #13      ; MOST OPTIONS RETURN TO HERE
6CC4:20 A8 FC  157 STALL6 JSR      WAIT     ; STALL FOR DISPLAY TIME
6CC7:CA      158      DEX      ;
6CC8:D0 FA      159      BNE      STALL6   ;

6CCA:20 58 FC  161      JSR      HOME      ; ERASE OLD SCREEN
6CCD:A2 28      162      LDX      #$28      ;
6CCF:20 7B 6E  163      JSR      QUIP     ; BLORK
6CD2:4C B9 6C  164      JMP      DOOPT     ; AND REPEAT

```

## PROGRAM RM-6, CONT'D . . .

```

6CD5:          167 ;      *** THE ACTUAL TASKS ***

6CD5:20 6B 66 169 TASKA JSR IMPRINT; TASK A
6CD8:C1 D2 D4 170      ASC      "ARTESIA"
6CDB:C5 D3 C9
6CDE:C1
6CDF:00          171      DFB      X
6CEC:60          172      RTS      ;

6CE1:20 6B 66 174 TASKB JSR IMPRINT; TASK B
6CE4:C2 CF CE 175      ASC      "BONITA"
6CE7:C9 D4 C1
6CEA:00          176      DFB      X
6CEB:60          177      RTS      ;

6CEC:20 6B 66 179 TASKC JSR IMPRINT; TASK C
6CEF:C3 CC C9 180      ASC      "CLIFTON"
6CF2:C6 D4 CF
6CF5:CE
6CF6:00          181      DFB      X
6CF7:60          182      RTS      ;

6CF8:20 6B 66 184 TASKD JSR IMPRINT; TASK D
6CFB:C4 D5 CE 185      ASC      "DUNCAN"
6CFE:C3 C1 CE
6D01:00          186      DFB      X
6D02:60          187      RTS      ;

6D03:20 6B 66 189 TASKE JSR IMPRINT; TASK E
6D06:C5 C4 C5 190      ASC      "EDEN"
6D09:CE
6D0A:00          191      DFB      X
6D0B:60          192      RTS      ;

6D0C:20 6B 66 194 TASKF JSR IMPRINT; TASK F
6D0F:C6 D2 C1 195      ASC      "FRANKLIN"
6D12:CE CB CC
6D15:C9 CE
6D17:00          196      DFB      X
6D18:60          197      RTS      ;

```

## PROGRAM RM-6, CONT'D . . .

6D19:20	6B 66	200	TASKG	JSR	IMPRINT;	TASK G
6D1C:C7	D5 D4	201		ASC		"GUTHRIE"
6D1F:C8	D2 C9					
6D22:C5						
6D23:00		202		DFB		X
6D24:60		203		RTS		;
6D25:20	6B 66	205	TASKH	JSR	IMPRINT;	TASK H
6D28:C8	C5 CC	206		ASC		"HELIOGRAPH"
6D2B:C9	CF C7					
6D2E:D2	C1 D0					
6D31:C8						
6D32:00		207		DFB		X
6D33:60		208		RTS		;
6D34:20	6B 66	210	TASKI	JSR	IMPRINT;	TASK I
6D37:C9	CE C4	211		ASC		"INDIAN SPRINGS"
6D3A:C9	C1 CE					
6D3D:A0	D3 D0					
6D40:D2	C9 CE					
6D43:C7	D3					
6D45:00		212		DFB		X
6D46:60		213		RTS		;
6D47:20	6B 66	215	TASKJ	JSR	IMPRINT;	TASK J
6D4A:CA	C1 C3	216		ASC		"JACKSON ESTATES"
6D4D:CB	D3 CF					
6D50:CE	A0 C5					
6D53:D3	D4 C1					
6D56:D4	C5 D3					
6D59:00		217		DFB		X
6D5A:60		218		RTS		;
6D5B:20	6B 66	220	TASKK	JSR	IMPRINT;	TASK K
6D5E:CB	CC CF	221		ASC		"KLONDYKE"
6D61:CE	C4 D9					
6D64:CB	C5					
6D66:00		222		DFB		X
6D67:60		223		RTS		;
6D68:20	6B 66	225	TASKL	JSR	IMPRINT;	TASK L
6D6B:CC	C9 D4	226		ASC		"LITTLE TULSA"
6D6E:D4	CC C5					
6D71:A0	D4 D5					
6D74:CC	D3 C1					
6D77:00		227		DFB		X
6D78:60		228		RTS		;

## PROGRAM RM-6, CONT'D . . .

6D79:20	6B 66	231	TASKM	JSR	IMPRINT;	TASK M
6D7C:CD	CF D2	232		ASC		"MORENCI"
6D7F:C5	CE C3					
6D82:C9						
6D83:00		233		DFB		X
6D84:60		234		RTS		;
6D85:20	6B 66	236	TASKN	JSR	IMPRINT;	TASK N
6D88:CE	C1 C3	237		ASC		"NACHES"
6D8B:C8	C5 D3					
6D8E:00		238		DFB		X
6D8F:60		239		RTS		;
6D90:		241 ;			TASK O	DEFAULTS TO INCTRAP
6D90:20	6B 66	243	TASKP	JSR	IMPRINT;	TASK P
6D93:D0	C9 CD	244		ASC		"PIMA"
6D96:C1						
6D97:00		245		DFB		X
6D98:60		246		RTS		;
6D99:		248 ;			TASK Q	DEFAULTS TO INCTRAP
6D99:20	6B 66	250	TASKR	JSR	IMPRINT;	TASK R
6D9C:D2	CF D0	251		ASC		"ROPER LAKE"
6D9F:C5	D2 A0					
6DA2:CC	C1 CB					
6DA5:C5						
6DA6:00		252		DFB		X
6DA7:60		253		RTS		;
6DA8:20	6B 66	255	TASKS	JSR	IMPRINT;	TASK S
6DAB:D3	C1 C6	256		ASC		"SAFFORD"
6DAE:C6	CF D2					
6DB1:C4						
6DB2:00		257		DFB		X
6DB3:60		258		RTS		;
6DB4:20	6B 66	260	TASKT	JSR	IMPRINT;	TASK T
6DB7:D4	C8 C1	261		ASC		"THATCHER"
6DBA:D4	C3 C8					
6DBD:C5	D2					
6DBF:00		262		DFB		X
6DC0:60		263		RTS		;
6DC1:		265 ;			TASK U	DEFAULTS TO INCTRAP



## PROGRAM RM-6, CONT'D . . .

```
6DC1:20 6B 66 268 TASKV JSR IMPRINT; TASK V
6DC4:D6 C9 D2 269 ASC "VIRDEN"
6DC7:C4 C5 CE
6DCA:00 270 DFB X
6DCB:60 271 RTS ;

6DCC:20 6B 66 273 TASKW JSR IMPRINT; TASK W
6DCF:D7 C8 C9 274 ASC "WHITLOCK CIENEGA"
6DD2:D4 CC CF
6DD5:C3 CB A0
6DD8:C3 C9 C5
6DDB:CE C5 C7
6DDE:C1
6DDF:00 275 DFB X
6DE0:60 276 RTS ;

6DE1: 278 ; TASK X DEFAULTS TO INCTRAP

6DE1:20 6B 66 280 TASKY JSR IMPRINT; TASK Y
6DE4:D9 CF D2 281 ASC "YORK VALLEY"
6DE7:CB A0 D6
6DEA:C1 CC CC
6DED:C5 D9
6DEF:00 282 DFB X
6DF0:60 283 RTS ;

6DF1: 285 ; TASK Z DEFAULTS TO INCTRAP
```

## PROGRAM RM-6, CONT'D . . .

```

6DF1:20 6B 66 288 INCTRAP JSR IMPRINT; INCLUSIVE DEFAULT TRAP
6DF4:D3 CF D2 289          ASC      "SORRY, PLEASE TRY"
6DF7:D2 D9 AC
6DFA:A0 D0 CC
6DFD:C5 C1 D3
6E00:C5 A0 D4
6E03:D2 D9
6E05:8D          290          DFB      C
6E06:D3 CF CD 291          ASC      "SOME OTHER LETTER"
6E09:C5 A0 CF
6E0C:D4 C8 C5
6E0F:D2 A0 CC
6E12:C5 D4 D4
6E15:C5 D2
6E17:00          292          DFB      X
6E18:60          293          RTS      ;

6E19:20 6B 66 295 ERRTRAP JSR IMPRINT; ILLEGAL KEY DEFAULT
6E1C:D4 C8 C1 296          ASC      "THATS NO LETTER"
6E1F:D4 D3 A0
6E22:CE CF A0
6E25:CC C5 D4
6E28:D4 C5 D2
6E2B:8D          297          DFB      C
6E2C:A0 A0 D9 298          ASC      " YOU TURKEY!"
6E2F:CF D5 A0
6E32:D4 D5 D2
6E35:CB C5 D9
6E38:A1
6E39:00          299          DFB      X
6E3A:60          300          RTS      ;

6E3B:20 2F FB 302 QUIT6 JSR INIT ; RESTORE NORMAL TEXT WINDOW
6E3E:20 58 FC 303 JSR HOME ; HOME CURSOR AND CLEAR SCREEN
6E41:68          304          PLA      ; BYPASS GILA; GO STRAIGHT
6E42:68          305          PLA      ; TO MONITOR OR CALLING CODE
6E43:60          306          RTS      ; FOR COMPLETE EXIT

```

## PROGRAM RM-6, CONT'D . . .

```

6E44:          309 ;          *** OPTION PICKER SUBROUTINE ***
6E44:          310 ;
6E44:          311 ;          FOR OTHER USES, THIS SUB HAS TO BE LINKED TO
6E44:          312 ;          YOUR OWN MATCHN MATCH NUMBER, YOUR MATCHF
6E44:          313 ;          CHARACTER MATCHER FILE AND YOUR JMPFLE VECTORS.
6E44:          314 ;

6E44:2C 10 C0 316 OPICK  BIT  KBDSTRB  ; LOCK OUT EARLY HITS
6E47:AD 00 C0 317 LOOK6  LDA  IOADR   ; GET KEY.  CAN'T USE KEYIN
6E4A:10 FB   318        BPL  LOOK6   ; BECAUSE WE NEED ESC COMMAND.
6E4C:2C 10 C0 319        BIT  KBDSTRB  ; RESET STROBE

6E4F:2C 6F 6E 321        JSR  FIXCASE  ; FORCE UPPERCASE

6E52:A2 0A   323        LDX  #10
6E54:20 7B 6E 324        JSR  QUIP    ; BLORK

6E57:AE 8A 6E 326        LDX  MATCHN  ; GET LEGAL NUMBER OF MATCHES
6E5A:DD 8B 6E 327 SCAN6  CMP  MATCHFL,X ; SEARCH FOR A MATCH
6E5D:F0 03   328        BEQ  GOTMTCH  ; FOUND
6E5F:CA     329        DEX          ; TRY NEXT
6E60:10 F8   330        BPL  SCAN6;

6E62:E8     332 GOTMTCH INX          ; MAKES ZERO A MISS
6E63:8A     333        TXA          ; GET JUMP VECTOR
6E64:0A     334        ASL  A        ; DOUBLE POINTER
6E65:AA     335        TAX          ;
6E66:BD A7 6E 336        LDA  JMPFL+1,X ; GET PAGE ADDRESS FIRST!
6E69:48     337        PHA          ; AND FORCE ON STACK
6E6A:BD A6 6E 338        LDA  JMPFL,X  ; GET POSITION ADDRESS
6E6D:48     339        PHA          ; AND FORCE ON STACK
6E6E:60     340        RTS          ; JUMP VIA FORCED SUBROUTINE RETURN

```

## PROGRAM RM-6, CONT'D . . .

```
6E6F:          343 ;          *** CASE FIXER SUBROUTINE ***

6E6F:          345 ;          TESTS THE ACCUMULATOR FOR A LOWERCASE
6E6F:          346 ;          CHARACTER.  IF PRESENT, FORCES UPPERCASE
6E6F:          347 ;          BY ADDING $20.  USES HIGH ASCII.

6E6F:C9 E1     349 FIXCASE CMP  #$E1          ; IF "a" OR MORE
6E71:90 07     350          BCC  NOFIX6          ;
6E73:C9 FB     351          CMP  #$FB          ; AND IF "z" OR LESS
6E75:B0 03     352          BCS  NOFIX6          ;
6E77:38       353          SEC                ; THEN SUBTRACT $20 TO
6E78:E9 20     354          SBC  #$20          ; FORCE UPPER CASE
6E7A:60       355 NOFIX6  RTS                ; AND RETURN

6E7B:          357 ;          *** QUIP SUBROUTINE ***
6E7B:          358 ;
6E7B:          359 ;          MAKES NOISE. X SETS THE PITCH.  THE
6E7B:          360 ;          PITCH IS PROPORTIONAL TO THE DURATION.
6E7B:          361 ;          WHICH IS OK FOR THIS SIMPLE USE BUT
6E7B:          362 ;          SHOULD BE AVOIDED MOST EVERYWHERE ELSE.

6E7B:48       364 QUIP   PHA                ; SAVE ACCUMULATOR
6E7C:A0 3C     365          LDY  #60           ; NUMBER OF CYCLES
6E7E:8A       366 NXT6   TXA                ; PITCH
6E7F:2C 30 C0  367          BIT  SPKR         ; WHAP SPEAKER
6E82:20 A8 FC  368          JSR  WAIT         ;
6E85:88       369          DEY                ; NEXT CYCLE
6E86:D0 F6     370          BNE  NXT6         ;
6E88:68       371          PLA                ; RESTORE ACCUMULATOR
6E89:60       372          RTS                ; AND EXIT
```

## PROGRAM RM-6, CONT'D . . .

```

6E8A:          375 ;      *** OPTION PICKER FILES ***

6E8A:          377 ;      MATCHN HOLDS THE NUMBER OF MATCHES.
6E8A:          378 ;      MATCHFL HOLDS THE LEGAL CHARACTERS.
6E8A:          379 ;      JUMPFL HOLDS THE JUMP VECTORS.
6E8A:          380 ;
6E8A:          381 ;      NOTE THAT ANY NUMBER OF CHARACTERS
6E8A:          382 ;      AND CONTROL COMMANDS MAY BE USED
6E8A:          383 ;      IN ANY ORDER, BUT THAT EACH MUST
6E8A:          384 ;      POSITION MATCH ITS JUMPFL VECTOR.

6E8A:1B        386 MATCHN DFB 27      ; NUMBER OF LEGAL MATCHES GOES HERE

6E8B:9B        388 MATCHFL DFB E      ; FOR ESCAPE

6E8C:C1 C2 C3 390          ASC        "ABCDEFGHIJKLM"
6E8F:C4 C5 C6
6E92:C7 C8 C9
6E95:CA CB CC
6E98:CD

6E99:CE CF D0 392          ASC        "NOPQRSTUVWXYZ"
6E9C:D1 D2 D3
6E9F:D4 D5 D6
6EA2:D7 D8 D9
6EA5:DA

6EA6:18 6E     394 JMPFL   DW   ERRTRAP-1 ; NOT A LEGAL KEY
6EA8:3A 6E     395         DW   QUIT6-1   ; EXIT ON ESCAPE
6EAA:D4 6C     396         DW   TASKA-1   ; DO LETTERED TASK
6EAC:E0 6C     397         DW   TASKB-1   ;
6EAE:EB 6C     398         DW   TASKC-1   ;
6EB0:F7 6C     399         DW   TASKD-1   ;
6EB2:02 6D     400         DW   TASKE-1   ;
6EB4:0B 6D     401         DW   TASKF-1   ;
6EB6:18 6D     402         DW   TASKG-1   ;
6EB8:24 6D     403         DW   TASKH-1   ;
6EBA:33 6D     404         DW   TASKI-1   ;
6EBC:46 6D     405         DW   TASKJ-1   ;
6EBE:5A 6D     406         DW   TASKK-1   ;
6EC0:67 6D     407         DW   TASKL-1   ;
6EC2:78 6D     408         DW   TASKM-1   ;
6EC4:84 6D     409         DW   TASKN-1   ;

```

## PROGRAM RM-6, CONT'D . . .

6EC6:F0 6D	412	DW	INCTRAP-1 ; LEGAL BUT NO TOWN
6EC8:8F 6D	413	DW	TASKP-1 ;
6ECA:F0 6D	414	DW	INCTRAP-1 ; LEGAL BUT NO TOWN
6ECC:98 6D	415	DW	TASKR-1 ;
6ECE:A7 6D	416	DW	TASKS-1 ;
6ED0:B3 6D	417	DW	TASKT-1 ;
6ED2:F0 6D	418	DW	INCTRAP-1 ; LEGAL BUT NO TOWN
6ED4:C0 6D	419	DW	TASKV-1 ;
6ED6:CB 6D	420	DW	TASKW-1 ;
6ED8:F0 6D	421	DW	INCTRAP-1 ; LEGAL BUT NO TOWN
6EDA:E0 6D	422	DW	TASKY-1 ;
6EDC:F0 6D	423	DW	INCTRAP-1 ; LEGAL BUT NO TOWN

\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS

## RANDOM NUMBERS

**pseudo-random number generator is fast, flexible, and free of defects**

Random numbers are essential for many computer uses, from the throw of a die, through animated game motions, to industrial simulations. How can you introduce randomness into your programs?

It turns out that there are two types of “random” numbers. A *real* random number is a number that can be one of many equally likely values. A *pseudo-random* number is the next number available in a contrived series that appears on the surface to be any one of many equally likely values . . .

**RANDOM NUMBER—**

**A number that can assume any one of many equally likely values.**

**PSEUDO-RANDOM NUMBER—**

**The next number available in a contrived series that appears on the surface to be any one of many equally likely values.**

The advantages of “real” random numbers is that they are truly

unpredictable. Disadvantages of real random numbers include that they are hard or inconvenient to generate and that there is no way to get the same random sequence back over again at a later time.

There is a very simple and very useful real random number generator built into your Apple. Any time you use the monitor subroutine KEYIN, there is a 16-bit counter involving locations RNDL and RNDH that gets incremented a random number of times. The randomness comes about since there is no control over how long a user waits between keystrokes. RNDL is located at \$4E and RNDH is located at \$4F on page zero. The monitor routines GETLN, GETLNZ, GETLN1, RDCHAR, and RDKEY all use KEYIN, so any of these can be used to fetch a new random number . . .

**To generate a real random number with your Apple, use the monitor routine KEYIN and then read the 16-bit true random result at \$4E and \$4F.**

The result is a truly random 16-bit number every time. For a new random number, have the user make repeated use of KEYIN, such as with a "HIT ANY KEY TO CONTINUE," or even start out with the flea-bitten "HI, WHAT'S YOUR NAME?" prompt.

If you don't need the full 16 bits, just mask off those you do want. One bit gives you a yes-no decision. A pair of bits generates the random digits from 0-3 and so on. For a RND(6), do a RND(8) instead, and, if you get a 6 or 7 result, go fish again. Or, better yet, you could also write your own version of GETKEY that counts your own base six counter round and round.

Same goes for any other modulo.

By modulo, we mean . . .

**MODULO—**  
**The "N" in RND (N).**  
**Note that RND(N) returns with one of N possible values, ranging from ZERO to ONE LESS THAN N.**

Uh, better repeat that. The modulo is the total number of different random numbers you can get back. Since zero is always one of them, the range of numbers will go from zero to  $N-1$ .

You never get a value of  $N$  for RND(N).

At any rate, using RNDL and RNDH, or else your own software counter for true randomness is very simple. But, there are at least two big disadvantages.

First and worst, the user must hit a key for every new random number you need. This gets old fast if more than a dozen selections are involved. Sometimes you can disguise what's happening in a game where lots of keystrokes are involved, but not often.

Secondly, this is a slow process that takes many milliseconds. You can generate pseudo-random numbers hundreds or even thousands of times faster.



And, finally, there is no way to get the same random numbers back again in the same sequence, for replays, or for “noise that repeats.”

So, while you have a true random number generator in your Apple and while it is very simple to access, you may not be able to do very much with it.

### What About Applesoft’s RND?

The advantages of pseudo-random number sequences are that they are easy to generate, and you can easily get the same short and apparently “random” sequence back as often as you like. This is handy for replaying a hand of cards, or to provide “noise that repeats” for industrial testing. You can also do this much faster than you can waiting for someone to press a key.

Applesloth has a subroutine in it that is a failed attempt at pseudo-random number generation.

By now, just about everyone knows that there is a fatal flaw in the Applesloth random number generator, that causes things to repeat in an annoying and frustratingly short way. And, no, the published fixes don’t help enough to be useful. So, besides it taking forever to generate a random number, this subroutine simply does not work . . .

APPLESOFT RND AIN'T.  
DON'T USE IT!

The fundamental problem is twofold. First, and more or less fixable, the Applesloth RND function does not “reseed” itself every time. The published repairs help this bunches, by using RNDL and RNDH as seeds.

Secondly, and fatally, any pseudo-random sequence generator is supposed to work by making the sequence so long that the numbers will apparently “never” repeat. For many argument values, the Applesloth RND generator does in fact generate an acceptably long sequence. But there are some exactly wrong magic values that repeat in as short as 200 or fewer values! And, as anyone who has used RND knows, these short sequences happen often enough to be a serious problem.

Actually, it is super difficult to fake generation of “random” numbers. There is level upon level of subtlety in the math involved in proving that any system for generating pseudo-random numbers is in fact able to provide truly random results.

What we should be worried about is something useful enough to appear random, even if it might eventually fail some exotic randomness test. It turns out that there is a very simple and devastatingly powerful way to test for randomness. Just put random dots on the HIRES screen. If the screen turns white, you are well on your way to having a good random number generator. If it gets lines, large patterns, or shading in it during this test, you have preferential numbers. If the screen “sticks” and never gets to all white, your sequence is too short to be useful and is repeating itself.

This simple scheme uses your eye as an optical correlator to really pull any nonrandomness right out of the woodwork.

Applesloth's RND always fails the screen test. Sometimes it fails it quickly, "sticking" after as few as 200 dots. Other times, you will get thousands of dots on the screen before the sequence repeats. The worst results are gotten by rerunning the same sequence over and over again.

Want to try it? . . .

```
3  REM
      DEMO TO SHOW WHY RND AINT

4  REM
      * RUN IT TILL IT STICKS *

5  HGR : HCOLOR = 3: REM

10 X = 280 * RND (1): Y = 192 * RND
    (1): HPLOT X,Y: GOTO 10
```

There are a few [J]'s in and amongst the code in this listing for pretty printing. Leave them off if you care to. Unless you immediately happen into the short sequences, the program may have to run a few minutes before it sticks.

Actually, to be fair, Applesloth is stuck with doing floating point random number generation, which is a far stickier problem than simply generating one number from a small integer field.

### An Integer Pseudo-Random Generator

Let's instead worry about generating integer pseudo-random numbers. The method we will show you easily handles any value from RND (2) to RND (255), and is extremely fast. It passes the screen-fill test with flying colors.

First, some theory. We will use a method called the *shift register pseudo-random sequence generator* method. This one is detailed both in the *TTL Cookbook* and the *CMOS Cookbook* (Sams 21035 and 21398).


There is a hardware beastie called a shift register that can be made to behave like a counter. By taking certain high taps off the shift register and EXCLUSIVE-ORing them together and feeding these back to the input, you can generate a very long sequence.

Very handily, any tests you make on a short burst in the sequence will lead you to believe you have a true random number generator. The optimum feedback connections lead to a *maximal length* sequence, which turns out to be one less than two raised to the number of stages in use.

To get "random" numbers, you keep picking up new numbers in the sequence, or else jump to some other wildly different place in the series. To get replays or noise that repeats, you start over again at the same point in the series you did before.

We will use a 31-stage pseudo-random register since the feedback needed is simpler than that needed by a 32-stage one. The hardware we are going to synthesize with software looks like so . . .

## A HARDWARE WAY TO GENERATE "RANDOM" NUMBERS:



There are 31 stages to our register. We take the output from stage 31 and EXCLUSIVE-OR it with the output from stage 28. The EOR of these taps then becomes the new value fed back to the input. These stage taps are "magic" values; anything else won't give you a super long series. We've shown this as a "shift-left" register, so we can be comparable to the replacement software we are about to use.

The sequence you get is one less than  $2^{31}$ , which translates to 2,147,483,647 counts before repeating. The variable sequence length of the Applesloth code is avoided, since you have one and only one long sequence, rather than bunches, a few of which can end up short.

This shift register can be thought of as a bit pipe or stream with two billion marbles in it, half red and half white. Grab any four marbles in sequence and you have a 4-bit random number. Grab the next four and you have a new 4-bit "random" number, and so on. In this case, you can get half a billion different 4-bit random numbers in sequence before the same marbles start coming back out. And, in fact, you will get four different half billion number sequences that are predictably related but not the same, since you are one marble short at the end of the first run, and so on.

Bunches, at any rate.

There is only one little gotcha to using a generator like this. What about the missing count? It turns out that . . .

### A GOTCHA—

A pseudo-random sequence generator will hang if it ever gets into the "all zeros" state.

**DON'T LET THIS HAPPEN!**

Now, the odds are only one in two billion of this ever happening, but you should know about it, and should prevent this hangup from ever happening. All you do is make sure there is a one somewhere in your shift register before you begin.

We will use software rather than hardware here. Set aside four bytes for the needed 31 bits. Use the EOR command for the EXCLUSIVE-OR logic, and use shift commands to move the bits from stage to stage.

### Some Code

It takes more than just a pseudo-random generator to make a good random number generation system.

First, we should have some way of initializing or reseeding the PSR 4-byte shift register. We do this by grabbing two bytes from RNDL and RNDH that are truly random, and by grabbing two more bytes off the last PSR state.

Secondly, we need some way to get an old sequence back for replays and noise that repeats. To do this, we keep a copy of the old reseeding in a separate 4-byte seed register. For a new sequence, you load the PSR from the reseeder. For a "used" or repeat sequence, you reload the PSR from the seed register.


Thirdly, we need some way to deal with nonbinary numbers. A RND (32) is fairly trivial, since 32 is a binary number, and we expect a result anywhere between 0 and 31. To do this, just whump the PSR register five times, once for each bit, and read the bits with a \$1F mask (that's 0001 1111 in binary) to get your result. For different binary lengths, use different mask lengths. The magic mask values are \$01, \$03, \$07, \$0F, \$1F, \$3F, \$7F, and \$FF.

But what about a RND (26)?

Here we expect a result between decimal 0 and 25, or between hex \$00 and \$19. What you do is use a mask to grab more than enough bits off the PSR, and then compare the result. If the result is in range, use it. If not, go fish. Repeat the process as often as you have to.

Which I'm not very proud of, but it works. For nonbinary values, there will be some chance of having to repeat the process. This chance is always less than 50 percent worst case, and typically, is much better. So, you will still get a fast result on any RND choice although binary values will be the fastest.

Since there are lots of pieces to this randomizer, let's first look at our working stashes to see what they tell us . . .

**STASHES USED BY RANDOM:**

There are fourteen stash values involved.

The actual PSR generator is labeled PSR1 through PSR4. We input to the low bit of PSR1 and feedback from bits 28 and 31 that are stashed in PSR4.

There are four seed bytes used to hold the previous starting point for the PSR sequence. These are called SEED1 through SEED4. These locations are seeded from the monitor's RNDL and RNDH.

The location called MODULO holds your RND argument. For instance, on a single die, use a MODULO value of six. In return, you will get one of the six possible equiprobable states from zero to five back. MODULO must be set on first use, but if you want the same random range over and over again, you do not have to change it.

The locations called RSIZE and BSIZE take some explanation, since they are the key to generating nonbinary random values. BSIZE is a mask of enough ones to equal one less than the next higher binary power of the number you are after. That's one of those magic \$01, \$03, \$07 . . . through \$FF values. BSIZE is automatically calculated for you when and as needed. RSIZE is a save of the number of PSR advances needed to get enough bits to handle your MODULO.

For instance, on a die, BSIZE will be a \$07, or binary %0000 0111, while RSIZE will be three. Why? Because it will take three bits to generate one of the numbers from zero to five. Should we overdo ourselves and get a six or seven result, we go fish and try again. The odds of hitting a legal value in this case are 3/4 of the time on the first try, and 15/16 of the time by the second try.

The reason you want to keep BSIZE as small as possible is so your odds of a hit are high. If, instead, you tried for six values out of a possible 256, your odds on a first-try hit will be a miniscule 6/256. The rea-

son for a separate save of RSIZE is so you do not have to recalculate BSIZE for each entry.

Which speeds things up bunches.

There are several places where our code *falls through* to another routine . . .

**FALLING THROUGH—**  
**Code that automatically goes on and does a second task.**  
**You also have the option of doing only the second task by itself.**

There are three parts to the pseudo-random generator code. These are the reseeder, the N initializer, and the actual PSR generator.

Each part is simple enough that you should be able to work up your own flowcharts.

The reseeder is used to move your position in the PSR sequence either to where you last started counting, or else to some wildly new point.

You should always JSR to this code anytime you want to start randomizing something new. If you do a JSR RESEED, you will shuffle the deck and begin at some unknown point in the PSR sequence. If you do a JSR RESET, you will reload the last seed value you used. Use RESEED for something entirely new. Use RESET to repeat the last sequence of random numbers for a replay or for noise that repeats.

Note how RESEED falls through to RESET. Note also that we make sure that PSR2 is not a zero value. If it is, we force it to one. This is one heavy way to be sure that you never hit the all ones gotcha in your PSR generator.

Every time you start up, or every time you change your modulo, you will have to activate the N initializer. Do this by a JSR to RANDOM, after putting the number of possible values you are after into MODULO. MODULO must be at least one. If it is zero, an error trap increments it.

Now, the code in the N initializer is admittedly obtuse, but this is what it does: Your modulo is scanned to generate a BSIZE mask with just enough sequential ones in it to equal or exceed your modulo value. At the same time, the number of bits involved is saved as RSIZE.

For instance, say you want RND (10). Modulo` will be ten, and you expect the ten digits from zero to nine back. BSIZE will be %0000 1111, since this is the smallest mask you can have that can isolate all the digits from zero to nine. RSIZE will be four, since four random bits are needed from the PSR generator.

The N initializer falls through to the “real” PSR generator. You have to use this initializer any time you first begin or any time you change your modulo.

There are two parts to the “real” PSR generator. The first half, labeled REUSEN, gets enough bits to be equal to or more than your modulo.

To do this, REUSEN first “aligns” bit 28 to bit 31 of PSR4 using the accumulator to shift bit 28 over three places. An EOR then computes the feedback term. This particular EOR term gets shifted into the carry.

Note that there are seven worthless EOR bit results calculated at the same time. These are simply ignored. The good result ends up in the carry flag; everything else gets flushed.

Our carry flag now holds our feedback product. To shift our shift register, you move carry into the least significant bit of PSR1 and shift the rest of PSR1's bits one to the left. The high bit now goes into the carry. Now shift, in turn PSR2, PSR3, and PSR4. The net result is that you faked a pseudo-random shift register with software.

The PSR is shifted as often as you have to, once for each count of RSIZE. Three whaps for a die, four for modulo ten, and so on.

At this point, enough bits have been randomized in PSR1 to give you a totally new number equal to or larger than your modulo.

The second half of the PSR process is called RANGE. Its purpose is to see if you are within your modulo with the present random value in PSR1. If you are in range, you are finished. If not, you have to repeat the process as often as you need to for a useful result. As we've seen, the odds on a hit are always greater than 50 percent and are usually much greater.

RANGE grabs the value in PSR1 and masks it with BSIZE. This cuts the number down to size, such as to four bits for a modulo of ten. The same four bits could be used for any modulo from nine through sixteen.

The result in the accumulator is then compared to MODULO. If you are *less than* MODULO, then your value is acceptable. If you are *equal to or greater than* MODULO, then your present value is no good, and you need another trip back through the PSR.

Two minor points. Note that you do not have to go back through the N initializer for a repeat trip, since you already know and have saved BSIZE and RSIZE. This speeds things up considerably. Secondly, note that you always want less than MODULO as a result, because of a possible zero answer. To repeat, if your MODULO is six, you get any of the six different values of zero, one, two, three, four, or five. You do *not* want an answer of "six" for a MODULO of six, since this is the *seventh*, and not the sixth possible value.

Summing up, to generate a "random" number, put the range of that number into MODULO. If this is your first time through, do a JSR RESEED. If you want to repeat a previous series, do a JSR RESET. Then do a JSR RANDOM. Your result ends up in the accumulator for machine language use, and in HOLD either for high level language access or for future reference.

If you want to use the same modulo over again, do a JSR REUSEN. This is much faster.

The companion demo is called FILL. It fills the HIRES screen the same way that WHY RND AIN'T didn't. Note particularly the speed difference, how clean the process is, and how you eventually get to a totally white screen.

Even this speed test is hardly fair, since we are still using the ludicrously slow Applesloth H PLOT subroutines in the demo. You can go much faster if you add your own custom H PLOT code.

You can extend your modulo to 511 by making two trips to RANDOM. To do this, divide the *even* part of your modulo by two. Generate this value and double it. Then do a separate RND (2) to pick even or odd results.

**MIND BENDERS**

- Show how to eliminate the repeat trips for nonbinary N.
- What is the actual speed involved in generating a random number?
- How can you use a PSR generator to generate speaker noise?
- Why and how does a 23-bit PSR fail the screen-fill test?
- Can you think of any uses for shorter or longer PSR generators?



**PROGRAM RM-7  
RANDOM NUMBERS**

----- NEXT OBJECT FILE NAME IS RANDOM

6F00:           3           ORG \$6F00           ; PUT MODULE #7 AT \$6F00

```

6F00:           5 ; *****
6F00:           6 ; *
6F00:           7 ; *           -< RANDOM >-           *
6F00:           8 ; *           (PSEUDORANDOM INTEGER GENERATOR)       *
6F00:           9 ; *           VERSION 1.0 ($6F00-$6FB2)           *
6F00:          10 ; *           1-12-83                               *
6F00:          11 ; *           .....*
6F00:          12 ; *           COPYRIGHT C 1983 BY               *
6F00:          13 ; *           DON LANCASTER AND SYNERGETICS       *
6F00:          14 ; *           BOX 1300, THATCHER AZ., 85552       *
6F00:          15 ; *           ALL COMMERCIAL RIGHTS RESERVED     *
6F00:          16 ; *           *****
6F00:          17 ; *
6F00:          18 ; *
6F00:          19 ; *
6F00:          20 ; *
6F00:          21 ; *
6F00:          22 ; *
6F00:          23 ; *****

```

6F00:           25 ;           \*\*\* WHAT IT DOES \*\*\*

```

6F00:           27 ;       THIS MODULE GIVES YOU A PSEUDORANDOM INTEGER FROM A
6F00:           28 ;       FIELD OF N. N CAN RANGE FROM 2 TO 255.
6F00:           29 ;

```

6F00:           31 ;           \*\*\* HOW TO USE IT \*\*\*

```

6F00:           33 ;       TO RESEED (INITIALIZE) FROM A TRUE RANDOM NUMBER,
6F00:           34 ;       DO A JSR SEED WITH A JSR $6F2E OR A CALL 28462.
6F00:           35 ;
6F00:           36 ;       TO REPEAT AN OLD PSEUDORANDOM SERIES, DO A JSR RESET
6F00:           37 ;       BY DOING A JSR $6F44 OR A CALL 28484.
6F00:           38 ;
6F00:           39 ;       TO GET A PSEUDORANDOM VALUE:
6F00:           40 ;
6F00:           41 ;       FROM MACHINE LANGUAGE, PUT N IN THE ACCUMULATOR
6F00:           42 ;       AND THEN JSR RANDOM AT $6F5B. RND(N) RETURNS IN A.
6F00:           43 ;
6F00:           44 ;       FROM APPLESOFT, STORE N IN MODULO AT 28593
6F00:           45 ;       AND THEN CALL RANDHL AT 28504. RND(N) ENDS
6F00:           46 ;       UP IN HOLD AT 28594.

```

## PROGRAM RM-7, CONT'D. . .

```
6F00:          49 ;          *** GOTCHAS ***
6F00:          51 ;  HALF THE ORIGINAL RANDOM SEED COMES FROM RNDL AND
6F00:          52 ;  RNDH IN THE MONITOR.  THE OTHER HALF COMES FROM
6F00:          53 ;  THE PREVIOUS PSR SEQUENCE.
6F00:          54 ;  N VALUES ONE LESS THAN A BINARY POWER EXECUTE FASTEST.
6F00:          55 ;  APPLESOFT IS NEEDED FOR THE SCREENFILL DEMO.
6F00:          56 ;  THE A AND Y REGISTERS ARE USED BY THESE SUBS.

6F00:          58 ;          *** ENHANCEMENTS ***
6F00:          60 ;  THE DEMO "FILL" LETS YOU FILL THE HIRES SCREEN RANDOMLY.
6F00:          61 ;  RUN IT WITH A JSR $7E00 OR A CALL 332256.
6F00:          62 ;

6F00:          64 ;          *** RANDOM COMMENTS ***
6F00:          66 ;  VALUES OF N THAT ARE NOT EQUAL TO ONE LESS THAN A
6F00:          67 ;  POWER OF TWO MAY NEED REPEAT TRIPS THROUGH THE PSR
6F00:          68 ;  SEQUENCER.  THIS IS DONE AUTOMATICALLY.  THE PROBABILITY
6F00:          69 ;  OF A HIT ALWAYS EXCEEDS 50% WORST CASE PER PASS AND
6F00:          70 ;  IS USUALLY MUCH HIGHER.
6F00:          71 ;
```

## PROGRAM RM-7, CONT'D . . .

```
6F00:          74 ;          *** HOOKS ***

F3E2:          76 HGR      EQU  $F3E2      ; APPLESOFT CLEAR TO HIRES ONE
F457:          77 HPLT     EQU  $F457      ; APPLESOFT HIRES PLOT
C000:          78 IOADR    EQU  $C000      ; KEYBOARD
C010:          79 KBSTR    EQU  $C010      ; KEYBOARD RESET
004E:          80 RNDL     EQU  $4E        ; RANDOM NUMBER LOW
004F:          81 RNDH     EQU  $4F        ; RANDOM NUMBER HIGH
F6EC:          82 SETHCOL  EQU  $F6EC      ; APPLESOFT HIRES COLOR SET
C050:          83 TEXT     EQU  $C050      ; TEXT SCREEN

6F00:          85 ;          *** CONSTANTS ***

0003:          87 COLOR    EQU  $03        ; FOR A WHITE PLOT
```

## PROGRAM RM-7, CONT'D . . .

```
6F00:          90 ;          *** SCREENFLL DEMO ***

6F00:          92 ;          THIS DEMO FILLS THE HIRES SCREEN ONE RANDOM
6F00:          93 ;          DOT AT A TIME.
6F00:          94 ;
6F00:          95 ;
6F00:          96 ;
6F00:          97 ;

6F00:20 E2 F3   99 FILL   JSR  HGR          ; CLEAR HIRES SCREEN
6F03:A2 03     100       LDX  #COLOR      ; PICK COLOR (03=WHITE)
6F05:20 EC F6   101       JSR  SETHCOL     ;

6F08:20 2E 6F   103       JSR  RESEED     ; SEED PSR FROM RNDL,RNDH

6F0B:A9 BF     105 PLOTDOT LDA  # $BF      ; 191 DOTS HIGH
6F0D:8D B1 6F   106       STA  MODULO     ;
6F10:20 5B 6F   107       JSR  RANDOM     ; GET RANDOM H
6F13:48         108       PHA          ; AND SAVE ON STACK
6F14:A9 FF     109       LDA  # $FF      ; 256 DOTS WIDE
6F16:8D B1 6F   110       STA  MODULO     ;
6F19:20 5B 6F   111       JSR  RANDOM     ; GET VERT
6F1C:A0 00     112       LDY  # $00      ; NO HISCREEN
6F1E:AA         113       TAX          ; TRANSFER H
6F1F:68         114       PLA          ; GET V
6F20:20 57 F4   115       JSR  HPLOT     ; PLOT DOT ON SCREEN
6F23:2C 00 C0   116       BIT  IOADR     ; READ KEYBOARD
6F26:30 02     117       BMI  EXIT7     ;
6F28:10 E1     118       BPL  PLOTDOT    ; CONTINUE IF NO KP
6F2A:2C 10 C0   119 EXIT7  BIT  KBSTR     ; RESET KEYBOARD
6F2D:60         120       RTS          ; AND QUIT
```

## PROGRAM RM-7, CONT'D . . .

```
6F2E:          123 ;          *** PSEUDORANDOM GENERATOR ***
6F2E:          125 ; THE PSEUDORANDOM GENERATOR IS A REGISTER THAT IS 31
6F2E:          126 ; BITS LONG. BITS 28 AND 31 ARE EXCLUSIVE ORED TO SET
6F2E:          127 ; THE NEXT MSB. SEQUENCE LENGTH IS 2,147,483,647.
6F2E:          128 ;
6F2E:          129 ;
6F2E:          130 ;
6F2E:          131 ;

6F2E:          133 ;          *** THE RESEEDER ***

6F2E:A5 4E     135 RESEED LDA RNDL      ; GET RANDOM NUMBER
6F30:8D A7 6F  136 STA SEED1    ; FROM MONITOR KEYBOARD RND
6F33:A5 4F     137 LDA RNDH      ; AND STORE FOR PSR SEED.
6F35:8D AA 6F  138 STA SEED4    ;
6F38:AD AD 6F  139 LDA PSR3      ; RESEED MIDDLE FROM OLD
6F3B:8D A8 6F  140 STA SEED2    ;
6F3E:AD AC 6F  141 LDA PSR2      ;
6F41:8D A9 6F  142 STA SEED3    ; AND FALL THRU TO RESET

6F44:A0 04     144 RESET LDY #S04     ; MOVE SEED TO PSR REGISTER
6F46:B9 A7 6F  145 NXT7  LDA SEED1,Y  ;
6F49:99 AB 6F  146 STA PSR1,Y  ;
6F4C:88        147 DEY           ;
6F4D:D0 F7     148 BNE NXT7     ;

6F4F:AD AC 6F  150 LDA PSR2      ; FORCE PSR SEED TO NONZERO
6F52:D0 03     151 BNE DONE7    ; BY FORCING NONZERO PSR2
6F54:EE AC 6F  152 INC PSR2      ;
6F57:60        153 DONE7 RTS         ; AND RETURN
```

## PROGRAM RM-7, CONT'D . . .

```

6F58:          156 ;          *** THE N INITIALIZER ***

6F58:AD B1 6F 158 RNDHL  LDA  MODULO      ; ENTER HERE FROM APPLESOFT
6F5B:9D B1 6F 159 RANDOM STA  MODULO      ; ENTER HERE FROM MACHINE LANGUAGE
6F5E:D0 05      160      BNE  BSCALC      ; N MUST NOT BE ZERO!
6F60:A9 02      161      LDA  #$02        ; USE N=2 MINIMUM
6F62:8D B1 6F 162      STA  MODULO      ;

6F65:A9 FF      164 BSCALC LDA  #$FF        ; INIT SIZE TO 255
6F67:8D AF 6F 165      STA  BSIZE        ; ENOUGH ONES HERE > MODULO
6F6A:A0 08      166      LDY  #$08        ; FOR 8 BITS
6F6C:AD B1 6F 167      LDA  MODULO        ; GET MODULO AND CALCULATE
6F6F:2A      168 SMALLER ROL  A            ; NEXT LARGER
6F70:B0 0C      169      BCS  ADVANCE      ;
6F72:4E AF 6F 170      LSR  BSIZE        ; DIVIDE BY TWO
6F75:88      171      DEY                ; NEXT SMALLER
6F76:D0 F7      172      BNE  SMALLER      ;
6F78:8C B0 6F 173      STY  RSIZE        ; SAVE FOR RETRY

6F7B:          176 ;          *** THE ACTUAL PSR GENERATOR ***

6F7B:AC B0 6F 178 REUSEN LDY  RSIZE        ; RESTORE IF RETRY
6F7E:AD AE 6F 179 ADVANCE LDA  PSR4        ; GET HIGH PSR
6F81:0A      180      ASL  A            ; ALIGN BIT 28 TO 31
6F82:0A      181      ASL  A            ;
6F83:0A      182      ASL  A            ;
6F84:4D AE 6F 183      EOR  PSR4        ; AND EXCLUSIVE OR
6F87:0A      184      ASL  A            ; MOVE TO CARRY
6F88:0A      185      ASL  A            ;
6F89:2E AB 6F 186      ROL  PSR1        ; SHIFT LOW PSR
6F8C:2E AC 6F 187      ROL  PSR2        ; SHIFT NEXT PSR
6F8F:2E AD 6F 188      ROL  PSR3        ; AND ONCE MORE
6F92:2E AE 6F 189      ROL  PSR4        ; FINALLY THE HIGH BYTE
6F95:88      190      DEY                ; REPEAT FOR EVERY BIT IN BSIZE
6F96:D0 E6      191      BNE  ADVANCE      ;

6F98:AD AB 6F 193 RANGE  LDA  PSR1        ; GET VALUE
6F9B:2D AF 6F 194      AND  BSIZE        ; MASK NEXT BINARY VALUE
6F9E:CD B1 6F 195      CMP  MODULO        ; IS VALUE TOO BIG?
6FA1:B0 D8      196      BCS  REUSEN      ; YES, TRY AGAIN
6FA3:8D B2 6F 197      STA  HOLD        ; SAVE VALID PSR
6FA6:60      198      RTS                ; AND EXIT

```

## PROGRAM RM-7, CONT'D . . .

```

6FA7:          201 ;          *** PSR REGISTERS ***

6FA7:          203 ;  SEEDL AND SEEDH HOLD THE STARTING SEED SHOULD YOU
6FA7:          204 ;  WANT TO RERUN THE SERIES.  PSR1, PSR2, PSR3, AND
6FA7:          205 ;  PSR4 FORM THE 23 BIT PSEUDORANDOM SEQUENCER.
6FA7:          206 ;
6FA7:          207 ;  BSIZE IS A SIZING MASK.
6FA7:          208 ;
6FA7:          209 ;  MODULO HOLDS THE VALUE N, WHILE HOLD KEEPS THE RANDOM (N)
6FA7:          210 ;

6FA7:AA        212 SEED1   DFB  $AA      ; SEED LOW VALUE
6FA8:AA        213 SEED2   DFB  $AA      ; SEED SECOND LOWEST
6FA9:AA        214 SEED3   DFB  $AA      ; SEED THIRD LOWEST
6FAA:AA        215 SEED4   DFB  $AA      ; HIGH SEED
6FAB:AA        216 PSR1    DFB  $AA      ; PSR LOW BYTE
6FAC:AA        217 PSR2    DFB  $AA      ; PSR SECOND LOWEST
6FAD:3B        218 PSR3    DFB  $3B      ; PSR THIRD LOWEST
6FAE:AA        219 PSR4    DFB  $AA      ; PSR HIGHEST
6FAF:FF        220 BSIZE   DFB  $FF      ; SAVE OF BINARY SIZE
6FB0:04        221 RSIZE   DFB  $04      ; YSAVE FOR RETRY

6FB1:07        223 MODULO   DFB  $07      ; MAXIMUM SIZE OF N
6FB2:00        224 HOLD    DFB  $00      ; SAVE OF PSR VALUE

```

## SHUFFLE

**a fast “random exchange”  
method of rearranging cards or  
number arrays**

There are lots of computer situations where you might like to take a pile of objects and rearrange them into some different order.

Shuffling a deck of cards is the most obvious example of this sort of thing. You might use playing cards for poker or blackjack simulations. Other times, the cards may have different symbols or messages on them. Tarot cards are an example, as are the *Chance* and *Community Chest* decks in a Monopoly simulation.

The things being shuffled need not be paper cards, of course. They could be tiles in a magic number game, letters in a word, the sequence in which new things appear, a maze in an adventure, or a journey into cryptography.

The fancy name for shuffling is *randomizing without replacement*. In randomizing without replacement, you simply rearrange a fixed array of values that you already have on hand. Once drawn from the deck, the four of clubs will not reappear.

The random number generator of the last ripoff module kept all the marbles in the pipe. You just cloned off the marbles you wanted. This was *randomizing with replacement*. In randomizing with replacement, the same value can come up over and over again.



Hence . . .

**Randomizing WITH Replacement—**

**Grabbing a random number without removing that number from being available for future grabs.**

**Rolling a die is an example.**

**Randomizing WITHOUT Replacement—**

**Grabbing a random number while also eliminating the availability of that number for future grabs.**

**Shuffling cards is typical.**

Note that these are totally different things. You'll get absurd results if you try to use the wrong one. Like only six different throws of a die before the die is "empty." Or the nine of spades dealt to you three cards in a row.

To throw some other terms at you, grabbing without replacement involves an *infinite pool* of numbers. Or at least an irrigation ditch full.

Grabbing with replacement involves a *finite pool* of numbers. These numbers are usually arranged into a fixed and rather small *array*. The array size on a playing card deck is usually 52.

The typical way that beginners try to shuffle things on their Apple has two very serious flaws. First, of course, they will be trying to use the Applesoft RND subroutine, which, as we have seen, is not.

Besides being rather slow.

We can easily fix this particular hassle by switching to the random number generator of the last ripoff module.

The second problem is more subtle. If you grab 52 random numbers in a row, you have to check each *new* number to make sure it was not duplicated before. This is no problem on the first card, and is trivial on the first few cards. But on, say card 50, the odds are 50/52 that you already have this card and have to go back again and again.

In fact, for your last card, you might need 52 *additional* tries to pick up only a 0.63 odds of finding the remaining card.

1/e and all that statistical stuff.

You, in fact, have to deal hundreds or even thousands of cards to be reasonably sure of getting 52 different ones. So, testing for duplicates is a bad scene because it takes ridiculously long and involves many wasted trips to the random number generator.

Let's work smarter and not harder. Do not try to take your numbers out of an infinite pool. Instead, take them out of a small and fixed array. Center your activities on rearranging the array.

Here is a good and fast way to shuffle a pile of something . . .

**TO REARRANGE N OBJECTS—**

**Take the object in the first location and interchange it with an object in another location in the array, chosen at random.**

**Then take the object in the second location and do the same thing.**

**Repeat this for all the locations.**

In other words, lay your 52 cards on the table. Grab the first card and interchange it with any card, picked at random. Next, grab the second card and interchange it with any card, again picked at random. Continue the process till you run out of cards.

Note two things. First, there are only 52 random numbers needed this way, since each random number gets used only once. Secondly, a card in some position will sometimes replace itself. This happens if the card in location number seven is interchanged with the random location number seven that just came up.

The odds on a card replacing itself are exactly the same as shuffling a real card deck and having the same card end up in the same position.

Which is rare but it certainly can happen. You can even get the deck back exactly the way you started. Odds on this are a tad low, though. The key point is that this random interchange method exactly duplicates a fair and thorough shuffle of real cards.

The same thing works for other shuffles. For a 15-tile magic square, you only interchange 15 values. You only swap six letters to jumble a six letter word, and so on.

Let's try it.

### A Shuffler

The subroutine called SHUFFLR will take an array named CARDECK of length ARNUM and reorder everything.

SHUFFLR does this by using the random number generator of the previous ripoff module. CARDECK is presently set up to hold 52 cards, and ARNUM equals decimal 52 or hex \$34.

The shuffling process is done by taking the first array value and interchanging it with an array value in a slot chosen at random. To find the exchange slot, you get a random number from 0 to 51 and do the exchange. The process gets repeated 52 times, thus swapping each card with some other card or itself at least once.

One of the array values being swapped is temporarily stashed on the stack. This handles the juggling process of moving two things between two locations without dropping either one of them.

To use SHUFFLR for other tasks, you just change the array values and the size of your array.

Note that SHUFFLR does not care what is inside each array slot. This lets you use meaningful codes for each array value. These codes are totally independent of the shuffling process.

How do you code a deck of cards?

One way to code the cards is to use one hex digit for the values

from ace through king. An obvious choice is to use \$X1 for an ace, \$X2 for a two, \$X9 for a nine, \$XA for a ten, \$XB for a jack, and so on. Let's use the least significant hex digit for this.

We will use the other hex digit to pick a suit. Say \$0X for hearts, \$1X for diamonds, \$2X for clubs, and \$3X for spades. Thus, the ace of spades will be coded \$31, while the king of diamonds will be a \$1D.

Clear?

A companion demo called DEALER will exercise your shuffler. The "S" key will shuffle the deck. The "R" key will repeat the previous shuffle for a replay. The "D" key, or optionally, the spacebar deals a card. The "Q" key quits the program for you.

We have used the short file printing method to handle text. It is the better choice here because we have lots of short and ordered words that we need in a more or less random access way. We are also under the nasty 256 character limit here. Use of a short file also saves dragging IMPRINT into the demo. It also gives you a chance to play with absolute indexed addressing.

The four options needed are simple enough that we will handle them by brute force, rather than using fancier option picker code.

We have also included a card counter. This one can be used for a position or a score, and does not need any hex-to-decimal or decimal-to-hex conversion. I'll leave it to you to puzzle out how this one works.

Naturally, a machine language randomizing-without-replacement module is far too fast to use as a real time playing card shuffle. So, we'll have to slow it down bunches. To do this, we will build the shuffler into a sound effect that mimics a deck being shuffled, and adjust the timing to "real" time.

Should you need something rearranged very quickly, be sure to defeat the sound effects. Or else adjust the effects to mimic what you are emulating.

Once again, the pseudo-random generator of the previous ripoff module is needed to get this module to work. So, be sure to have either RANDOM or THE WHOLE BALL OF WAX in your machine when using either the shuffler or the card demo.

**MIND BENDERS**

- What is the total time needed to shuffle a deck of 52 cards, with and without the sound effects?
- Add a HIRES or LORES graphics display of the playing cards.
- Show how to do an “instant solver” for those word jumble puzzles on a newspaper’s comics page.
- In a word guessing game that has a file of hundreds of words, show how to get each word just once yet in a different order each session.
- Why does the card number display work in decimal without needing any hex conversion?
- What changes are needed to make the demo professionally useful?

**PROGRAM RM-8  
SHUFFLE**

----- NEXT OBJECT FILE NAME IS SHUFFLER

7000:           3            ORG \$7000           ; PUT MODULE #8 AT \$7000

```

7000:           5 ; *****
7000:           6 ; *
7000:           7 ; *                   -< SHUFFLER >-           *
7000:           8 ; *
7000:           9 ; *   ( RANDOMIZING WITHOUT REPLACEMENT ) *
7000:          10 ; *
7000:          11 ; *           VERSION 1.0 ($7000-$7246)       *
7000:          12 ; *
7000:          13 ; *                   5-24-83                   *
7000:          14 ; *.....*
7000:          15 ; *
7000:          16 ; *                   COPYRIGHT C 1983 BY       *
7000:          17 ; *
7000:          18 ; *           DON LANCASTER AND SYNERGETICS   *
7000:          19 ; *           BOX 1300, THATCHER AZ., 85552   *
7000:          20 ; *
7000:          21 ; *           ALL COMMERCIAL RIGHTS RESERVED   *
7000:          22 ; *
7000:          23 ; *****

```

7000:           25 ;                   \*\*\* WHAT IT DOES \*\*\*

```

7000:           27 ;   THIS MODULE SHOWS YOU HOW TO SHUFFLE OR REARRANGE
7000:           28 ;   AN ARRAY OF CARDS, NUMBERS, LETTERS, OR OBJECTS.
7000:           29 ;

```

7000:           31 ;                   \*\*\* HOW TO USE IT \*\*\*

```

7000:           33 ;   TO USE THE SHUFFLER:
7000:           34 ;
7000:           35 ;           START YOUR ARRAY FILE WITH CARDECK AT $7213.
7000:           36 ;           PUT THE NUMBER OF ARRAY ELEMENTS IN ARNUM AT $710E.
7000:           37 ;           THEN JSR SHUFFLR AT $70F1. EQUIVALENT APPLESLOTH
7000:           38 ;           LOCATIONS ARE 29203, 28942, AND 28913.

```

```

7000:           40 ;   TO RUN THE CARD DEALER DEMO:
7000:           41 ;
7000:           42 ;           JSR DEALER AT $7000 OR CALL 28672.

```

## PROGRAM RM-8, CONT'D . . .

```
7000:      45 ;          *** GOTCHAS ***
7000:      47 ; THE RANDOM SUBROUTINE MUST BE PRESENT IN THE
7000:      48 ; MACHINE. PRELOAD "RANDOM" OR "THE WHOLE BALL
7000:      49 ; OF WAX" TO DO THIS.
7000:      50 ;
7000:      51 ; YOUR ARRAY FILE MUST BE PRELOADED WITH THE
7000:      52 ; PROPER VALUES.

7000:      54 ;          *** ENHANCEMENTS ***
7000:      56 ; WORDS, OBJECTS, OR OTHER TYPES OF CARDS ARE DONE
7000:      57 ; BY CHANGING THE MEANING AND SIZE OF YOUR ARRAY.
7000:      58 ;

7000:      60 ;          *** RANDOM COMMENTS ***
7000:      62 ; THIS SHUFFLE DEMO IS INTENDED TO SHOW THE PROCESS
7000:      63 ; INVOLVED. AN ACTUAL CARD PROGRAM HAS TO BE FAR
7000:      64 ; FRIENDLIER THAN THIS, AND SHOULD DISPLAY REAL CARDS.
7000:      65 ;
7000:      66 ; THE DEMO ALSO SHOWS HOW TO HANDLE SIMPLE SCORING
7000:      67 ; WITHOUT NEEDING HEX TO DECIMAL CONVERSION.
```

## PROGRAM RM-8, CONT'D . . .

```
7000:          70 ;          *** HOOKS ***

FDF0:          72 COUTL   EQU  $FDF0   ; OUTPUT TEXT TO SCREEN
FC58:          73 HOME    EQU  $FC58   ; CLEAR TEXT SCREEN AND HOME CURSOR
FB2F:          74 INIT    EQU  $FB2F   ; INITIALIZE TEXT SCREEN
C000:          75 IOADR   EQU  $C000   ; KEYBOARD INPUT LOCATION
C010:          76 KBDSTRB EQU  $C010   ; KEYBOARD STROBE RESET
FD1B:          77 KEYIN   EQU  $FD1B   ; MONITOR READKEY SUBROUTINE
FE80:          78 SETINV  EQU  $FE80   ; SET INVERSE SCREEN
FE84:          79 SETNORM EQU  $FE84   ; SET NORMAL SCREEN
C030:          80 SPKR    EQU  $C030   ; SPEAKER CLICK OUTPUT
FCA8:          81 WAIT    EQU  $FCA8   ; MONITOR TIME DELAY

6F5B:          83 RANDOM  EQU  $6F5B   ; RANDOM NUMBER INITIALIZER
6F2E:          84 RESEED  EQU  $6F2E   ; RANDOM NUMBER SEEDER
6F7B:          85 REUSEN  EQU  $6F7B   ; RANDOM NUMBER GENERATOR

0020:          87 WNDLFT  EQU  $20     ; LEFT SIDE OF SCROLL WINDOW
0021:          88 WNDWTH  EQU  $21     ; WIDTH OF SCROLL WINDOW
0022:          89 WNDTOP  EQU  $22     ; TOP OF SCROLL WINDOW
0023:          90 WNDBTM  EQU  $23     ; BOTTOM OF SCROLL WINDOW
0024:          91 CH      EQU  $24     ; CURSOR HORIZONTAL POSITION
0033:          92 PROMPT  EQU  $33     ; PROMPT SYMBOL

7000:          94 ;          *** TEXTFILE COMMANDS ***

0088:          96 B       EQU  $88     ; BACKSPACE
008D:          97 C       EQU  $8D     ; CARRIAGE RETURN
0084:          98 D       EQU  $84     ; DOS ATTENTION
009B:          99 E       EQU  $9B     ; ESCAPE
008A:          100 L      EQU  $8A     ; LINEFEED
0060:          101 P      EQU  $60     ; FLASHING PROMPT
0000:          102 X      EQU  $00     ; END OF MESSAGE
```

## PROGRAM RM-8, CONT'D . . .

```

7000:          105 ;      *** DEALIN DEMO ***

7000:          107 ;      THIS DEMO EXERCISES THE SHUFFLER
7000:          108 ;      ON A STANDARD DECK OF 52 CARDS.

7000:20 2F FB 110 DEALER JSR INIT      ; SET UP TEXT SCREEN
7003:20 58 FC 111        JSR HOME     ; AND CLEAR IT
7006:20 2E 6F 112        JSR RESEED   ; RESEED RANDOM
7009:AD 0E 71 113        LDA ARNUM    ; GET ARRAY NUMBER
700C:20 5B 6F 114        JSR RANDOM   ; INIT RANDOM

700F:A9 07      116        LDA #$07      ; TAB 7 TO RIGHT
7011:85 24      117        STA CH        ;
7013:20 80 FE 118        JSR SETINV   ; INVERSE TITLE
7016:A0 5E      119        LDY #>MS0-CV1 ; GET HEADER
7018:20 E3 70 120        JSR TEXT8   ; AND DISPLAY
701B:20 84 FE 121        JSR SETNORM  ; NORMAL TEXT
701E:A0 74      122        LDY #>MS1-CV1 ; GET SCREEN PROMPTS
7020:20 E3 70 123        JSR TEXT8   ; AND DISPLAY

7023:A9 07      125        LDA #$07      ; SET LOWSCREEN WINDOW
7025:85 22      126        STA WNDTOP   ;
7027:A9 05      127        LDA #$05      ;
7029:85 20      128        STA WNDLFT   ; TAB OVER TO CENTER
702B:A9 22      129        LDA #$22      ;
702D:85 21      130        STA WNDWTH   ;
702F:20 58 FC 131        JSR HOME     ; GET INSIDE WINDOW

7032:2C 10 C0 133 CMND8  BIT KBDSTRB  ; RESET KEYBOARD
7035:AD 00 C0 134 LOOK8  LDA IOADR   ; READ KEYBOARD
7038:10 FB      135        BPL LOOK8   ;
703A:2C 10 C0 136        BIT KBDSTRB  ;
703D:C9 E1      137        CMP #$E1    ; FORCE CASE
703F:90 02      138        BCC CSORT   ;
7041:E9 20      139        SBC #$20    ; SUBTRACT TO CHANGE CASE

7043:C9 D3      141 CSORT  CMP #$D3    ; S FOR SHUFFLE?
7045:F0 1D      142        BEQ SHUFF   ; YES
7047:C9 C4      143        CMP #$C4    ; D FOR DEAL ?
7049:F0 2E      144        BEQ DEAL    ;
704B:C9 A0      145        CMP #$A0    ; ALSO SPACE FOR DEAL
704D:F0 2A      146        BEQ DEAL    ;
704F:C9 D2      147        CMP #$D2    ; R FOR REPLAY?
7051:F0 17      148        BEQ REPLAY  ;
7053:C9 D1      149        CMP #$D1    ; Q FOR QUIT?
7055:F0 06      150        BEQ QUIT8   ;
7057:20 18 71 151        JSR EFFECT2  ; BLORK
705A:4C 32 70 152        JMP CMND8   ; TRY AGAIN FOR LEGAL KEY

```



## PROGRAM RM-8, CONT'D . . .

```
705D:          155 ;      *** QUIT EXIT ***
705D:20 2F FB 157 QUIT8 JSR INIT      ; OPEN WINDOW
7060:20 58 FC 158 JSR HOME      ; CLEAR SCREEN
7063:60      159      RTS          ; AND EXIT ON "Q"

7064:          161 ;      *** SHUFF PROCESSING ***

7064:          163 ;      THIS CODE SHUFFLES THE DECK AND
7064:          164 ;      RESETS THE CARD COUNTERS TO ONE.

7064:20 F1 70 166 SHUFF JSR SHUFFLR ; SHUFFLE THE DECK
7067:4C 6A 70 167 JMP  REPLAY  ; RESET COUNTERS

706A:          169 ;      *** REPLAY MODULE ***

706A:          171 ;      RESETS THE CARD COUNTER TO ZERO.

706A:A0 00      173 REPLAY LDY  #$00      ; RESET COUNTERS
706C:8C EF 70 174 STY  HEXCNT      ;
706F:C8          175 INY          ; ONE MORE FOR PEOPLE
7070:8C F0 70 176 STY  DECCNT      ;
7073:20 58 FC 177 JSR  HOME      ; CLEAR OLD CARDS
7076:4C 32 70 178 JMP  CMND8      ; GO GET NEXT COMMAND
```

## PROGRAM RM-8, CONT'D . . .

```

7079:          181 ;      *** DEAL PROCESSING ***

7079:          183 ;      THIS CODE TRYs TO DEAL A CARD IF
7079:          184 ;      THERE ARE ANY LEFT IN THE DECK.

7079:AD EF 70 186 DEAL   LDA  HEXCNT   ; GET NUMBER IN DECK (52)
707C:CD 0E 71 187       CMP  ARNUM    ; ANY CARDS LEFT?
707F:B0 5A 188       BCS  EMPTY8   ; NO, SAY SO

7081:A0 A5 190       LDY  #>MS2-CV1 ; SAY "CARD"
7083:20 E3 70 191       JSR  TEXT8   ;
7086:AD F0 70 192       LDA  DECCNT   ; GET TENS FOR CARD NUMBER
7089:4A 193       LSR  A           ; AND SHIFT FOUR TO RIGHT
708A:4A 194       LSR  A           ;
708B:4A 195       LSR  A           ;
708C:4A 196       LSR  A           ;
708D:F0 05 197       BEQ  LOWDEC    ; IS IT NONZERO?
708F:09 B0 198       ORA  #$B0     ; CHANGE TO ASCII
7091:20 F0 FD 199       JSR  COU1    ; AND PRINT IT
7094:AD F0 70 200 LOWDEC LDA  DECCNT   ; GET UNITS FOR CARD NUMBER
7097:29 0F 201       AND  #$0F     ; MASK TENS
7099:09 B0 202       ORA  #$B0     ; CHANGE TO ASCII
709B:20 F0 FD 203       JSR  COU1    ; AND PRINT IT

709E:A0 AB 205       LDY  #>MS3-CV1 ; SAY "IS THE"
70A0:20 E3 70 206       JSR  TEXT8   ; TO SCREEN

70A3:AE EF 70 208       LDX  HEXCNT   ; GET CARD
70A6:BD 13 72 209       LDA  CARDECK,X ; FROM DECK
70A9:48 210       PHA           ; AND SAVE FOR SUIT
70AA:29 0F 211       AND  #$0F     ; MASK SUIT
70AC:AA 212       TAX           ; USE AS INDEX
70AD:CA 213       DEX           ; MAKE ACE=1, NOT ZERO!
70AE:BC 2A 71 214       LDY  CARVAL,X ; GET SUIT NAME
70B1:20 E3 70 215       JSR  TEXT8   ; AND PRINT TO SCREEN

70B4:A0 B4 217       LDY  #>MS4-CV1 ; SAY "OF"
70B6:20 E3 70 218       JSR  TEXT8   ; AND PRINT IT

70B9:68 220       PLA           ; GET CARD BACK
70BA:4A 221       LSR  A           ; AND SHIFT TO RIGHT
70BB:4A 222       LSR  A           ;
70BC:4A 223       LSR  A           ;
70BD:4A 224       LSR  A           ;
70BE:AA 225       TAX           ; USE AS INDEX
70BF:BC 37 71 226       LDY  CARSUIT,X ; GET SUIT NAME
70C2:20 E3 70 227       JSR  TEXT8   ; AND PRINT IT

```

## PROGRAM RM-8, CONT'D . . .

```
70C5:A0 B9      230      LDY  #>MS5-CV1 ; GET PERIOD AND CR
70C7:20 E3 70   231      JSR  TEXT8     ; AND PRINT IT
70CA:EE EF 70   232      INC  HEXCNT   ; GO TO NEXT CARD
70CD:F8         233      SED          ; GO TO DECIMAL FOR SCORE
70CE:18         234      CLC          ;
70CF:AD F0 70   235      LDA  DECCNT   ; INCREMENT DECIMAL
70D2:69 01     236      ADC  #$01    ;
70D4:8D F0 70   237      STA  DECCNT   ;
70D7:D8         238      CLD          ; GET OUT OF DECIMAL!
70D8:4C 32 70   239      JMP  CMND8    ; GO GET NEXT COMMAND
```

```
70DB:A0 BD      241 EMPTY8 LDY  #>MS6-CV1 ; GET EMPTY MESSAGE
70DD:20 E3 70   242      JSR  TEXT8     ; PUT ON SCREEN
70E0:4C 32 70   243      JMP  CMND8    ; GO GET NEXT COMMAND
```

```
70E3:          245 ;      *** TEXT GENERATOR ***
```

```
70E3:          247 ;      THIS USES THE SHORT FILE METHOD TO PUT
70E3:          248 ;      MESSAGES ONLY ON THE SCREEN.
```

```
70E3:B9 3B 71   250 TEXT8  LDA  CV1,Y     ; GET NEXT CHARACTER
70E6:F0 06      251          BEQ  DONE8     ; TEST FOR $00
70E8:20 F0 FD   252          JSR  COUT1    ; OUTPUT TO SCREEN
70EB:C8         253          INY          ; GO TO NEXT CHARACTER
70EC:D0 F5      254          BNE  TEXT8     ; AND REPEAT
70EE:60         256 DONE8  RTS          ; RETURN WHEN FINISHED
```

```
70EF:          258 ;      *** CARD COUNTER STASH ***
```

```
70EF:00        260 HEXCNT  DFB  $00      ; HEX COUNT FOR MACHINE
70F0:01        261 DECCNT  DFB  $01      ; DECIMAL COUNT FOR PEOPLE
```

## PROGRAM RM-8, CONT'D . . .

```

70F1:          264 ;      *** SHUFFLER SUBROUTINE ***

70F1:          266 ;      THIS MODULE REARRANGES THE ARRAY CALLED CARDECK
70F1:          267 ;      AND WHOSE LENGTH IS STORED IN ARNUM.
70F1:          268 ;
70F1:          269 ;      THE RANDOM SUBROUTINE MUST BE PRESENT IN THE
70F1:          270 ;      MACHINE AND MUST BE PREVIOUSLY SEEDED AND
70F1:          271 ;      INITIALIZED.

70F1:AE 0E 71 273 SHUFFLR LDX  ARNUM      ; GET NUMBER OF SWAPS
70F4:CA          274          DEX          ; FOR ARRAY 0-51, NOT 1-52
70F5:20 7B 6F 275 NEXT8  JSR  REUSEN     ; GET RANDOM POSITION
70F8:A8          276          TAY          ; AND HOLD IN Y REGISTER
70F9:BD 13 72 277          LDA  CARDECK,X ; GET FIRST FIXED VALUE
70FC:48          278          PHA          ; STASH TO JUGGLE
70FD:B9 13 72 279          LDA  CARDECK,Y ; GET RANDOM NEXT VALUE
7100:9D 13 72 280          STA  CARDECK,X ; REPLACE NEXT WITH FIRST
7103:68          281          PLA          ; JUGGLE BACK
7104:99 13 72 282          STA  CARDECK,Y ; REPLACE FIRST WITH NEXT
7107:20 0F 71 283          JSR  EFFECT1  ; MAKE NOISE (OPTIONAL)
710A:CA          284          DEX          ; ONE LESS POSITION
710B:10 E8      285          BPL  NEXT8    ; REPEAT FOR EACH POSITION
710D:60          286          RTS         ; QUIT WHEN FINISHED

710E:          288 ;      *** SHUFFLER STASH ***

710E:34          290 ARNUM  DFB  52          ; NUMBER OF ELEMENTS IN ARAY

710F:          292 ;      *** SHUFFLER SOUND EFFECTS ***

710F:8A          294 EFFECT1 TXA          ; DECK SHUFFLING SOUND
7110:D0 02      295          BNE  NOZEROS  ; DISALLOW ZERO VALUE
7112:A9 01      296          LDA  #$01     ;
7114:0A          297 NOZEROS ASL  A        ; SLOW IT DOWN!
7115:20 A8 FC  298          JSR  WAIT     ; DELAY, THEN FALL THROUGH
7118:A9 05      299 EFFECT2 LDA  #$05     ; NUMBER OF CLICKS PER WHAP
711A:48          300 NEXTWP PHA          ; SAVE ON STACK
711B:2C 30 C0  301          BIT  SPKR    ; MOVE SPEAKER CONE
711E:A9 07      302          LDA  #$07     ; SET PITCH OF WHAP
7120:20 A8 FC  303          JSR  WAIT     ;
7123:68          304          PLA          ; GET CLICK COUNTER
7124:38          305          SEC          ;
7125:E9 01      306          SBC  #$01     ; AND COUNT DOWN
7127:D0 F1      307          BNE  NEXTWP  ;
7129:60          308          RTS         ; AND RETURN

```

## PROGRAM RM-8, CONT'D . . .

712A: 311 ; \*\*\* MESSAGE FILE \*\*\*

712A: 313 ; WE'LL USE THE SHORT FILE METHOD HERE SINCE  
712A: 314 ; RANDOM ACCESS OF A FEW SHORT AND FIXED  
712A: 315 ; MESSAGES ARE NEEDED.  
712A: 316 ;

712A: 318 ; \*\*\* MESSAGE POINTERS \*\*\*

712A:00	320	CARVAL	DFB	>CV1-CV1	; THESE POINT TO CARD VALUES
712B:04	321		DFB	>CV2-CV1	;
712C:08	322		DFB	>CV3-CV1	;
712D:0E	323		DFB	>CV4-CV1	;
712E:13	324		DFB	>CV5-CV1	;
712F:18	325		DFB	>CV6-CV1	;
7130:1C	326		DFB	>CV7-CV1	;
7131:22	327		DFB	>CV8-CV1	;
7132:28	328		DFB	>CV9-CV1	;
7133:2D	329		DFB	>CV10-CV1	;
7134:31	330		DFB	>CV11-CV1	;
7135:36	331		DFB	>CV12-CV1	;
7136:3C	332		DFB	>CV13-CV1	;

7137:41	334	CARSUIT	DFB	>CS0-CV1	; THESE POINT TO THE CARD SUITS
7138:48	335		DFB	>CS1-CV1	;
7139:51	336		DFB	>CS2-CV1	;
713A:57	337		DFB	>CS3-CV1	;

## PROGRAM RM-8, CONT'D . . .

```

7138:          340 ;      *** THE CARD VALUES ***

713B:C1 C3 C5  342 CV1   ASC      "ACE"
713E:00        343     DFB      X

713F:D4 D7 CF  345 CV2   ASC      "TWO"
7142:00        346     DFB      X

7143:D4 C8 D2  348 CV3   ASC      "THREE"
7146:C5 C5          349     DFB      X

7149:C6 CF D5  351 CV4   ASC      "FOUR"
714C:D2          352     DFB      X
714D:00

714E:C6 C9 D6  354 CV5   ASC      "FIVE"
7151:C5          355     DFB      X
7152:00

7153:D3 C9 D8  357 CV6   ASC      "SIX"
7156:00        358     DFB      X

7157:D3 C5 D6  360 CV7   ASC      "SEVEN"
715A:C5 CE          361     DFB      X
715C:00

715D:C5 C9 C7  363 CV8   ASC      "EIGHT"
7160:C8 D4          364     DFB      X
7162:00

7163:CE C9 CE  366 CV9   ASC      "NINE"
7166:C5          367     DFB      X
7167:00

7168:D4 C5 CE  369 CV10  ASC      "TEN"
716B:00        370     DFB      X

716C:CA C1 C3  372 CV11  ASC      "JACK"
716F:CB          373     DFB      X
7170:00

7171:D1 D5 C5  375 CV12  ASC      "QUEEN"
7174:C5 CE          376     DFB      X
7176:00

7177:CB C9 CE  378 CV13  ASC      "KING"
717A:C7          379     DFB      X
717B:00

```

## PROGRAM RM-8, CONT'D . . .

717C: 382 ; \*\*\* THE CARD SUITS \*\*\*

717C:C8 C5 C1	384 CS0	ASC	"HEARTS"
717F:D2 D4 D3			
7182:00	385	DFB	X
7183:C4 C9 C1	387 CS1	ASC	"DIAMONDS"
7186:CD CF CE			
7189:C4 D3			
718B:00	388	DFB	X
718C:C3 CC D5	390 CS2	ASC	"CLUBS"
718F:C2 D3			
7191:00	391	DFB	X
7192:D3 D0 C1	393 CS3	ASC	"SPADES"
7195:C4 C5 D3			
7198:00	394	DFB	X

7199: 396 ; \*\*\* TEXT SCREEN MESSAGES \*\*\*

7199:C3 C1 D2	398 MS0	ASC	"CARD SHUFFLING DEMO"
719C:C4 A0 D3			
719F:C8 D5 C6			
71A2:C6 CC C9			
71A5:CE C7 A0			
71A8:C4 C5 CD			
71AB:CF			
71AC:8D 8D 00	399	DFB	C,C,X
71AF:A8 D3 A9	401 MS1	ASC	"(S)HUFFLE, (D)EAL, (R)EPLAY, (Q)UIT ?
71B2:C8 D5 C6			
71B5:C6 CC C5			
71B8:AC A0 A8			
71BB:C4 A9 C5			
71BE:C1 CC AC			
71C1:A0 A8 D2			
71C4:A9 C5 D0			
71C7:CC C1 D9			
71CA:AC A0 A8			
71CD:D1 A9 D5			
71D0:C9 D4 A0			
71D3:BF			
71D4:8D 8D	402	DFB	C,C
71D6:AD AD AD	403	ASC	"----> "
71D9:BE A0			
71DB:60 88 8D	404	DFB	P,B,C,C,X
71DE:8D 00			

## PROGRAM RM-8, CONT'D . . .

71E0:C3 C1 D2	407 MS2	ASC	"CARD "
71E3:C4 A0			
71E5:00	408	DFB	X
71E6:A0 C9 D3	410 MS3	ASC	" IS THE "
71E9:A0 D4 C8			
71EC:C5 A0			
71EE:00	411	DFB	X
71EF:A0 CF C6	413 MS4	ASC	" OF "
71F2:A0			
71F3:00	414	DFB	X
71F4:AE	416 MS5	ASC	". "
71F5:8D 8D 00	417	DFB	C,C,X
71F8:A0 A0 A0	419 MS6	ASC	" SORRY, DECK IS EMPTY!"
71FB:D3 CF D2			
71FE:D2 D9 AC			
7201:A0 C4 C5			
7204:C3 CB A0			
7207:C9 D3 A0			
720A:C5 CD D0			
720D:D4 D9 A1			
7210:8D 8D 00	420	DFB	C,C,X



## PROGRAM RM-8, CONT'D . . .

```
7213:          423 ;      *** DECK OF CARDS ***

7213:          425 ;      THE LOW BYTE OF EACH ENTRY IS THE CARD
7213:          426 ;      VALUE WITH X1=ACE, X2=TWO, XA=TEN, ETC.
7213:          427 ;
7213:          428 ;      THE HIGH BYTE OF EACH ENTRY IS THE CARD
7213:          429 ;      SUIT WITH 0X=HEARTS, 1X=DIAMONDS, 2X=
7213:          430 ;      CLUBS, AND 3X=SPADES.

7213:01 02 03 432 CARDECK DFB          $01,$02,$03,$04,$05,$06,$07
7216:04 05 06
7219:07
721A:08 09 0A 433          DFB          $08,$09,$0A,$0B,$0C,$0D
721D:0B 0C 0D

7220:11 12 13 435          DFB          $11,$12,$13,$14,$15,$16,$17
7223:14 15 16
7226:17
7227:18 19 1A 436          DFB          $18,$19,$1A,$1B,$1C,$1D
722A:1B 1C 1D

722E:21 22 23 438          DFB          $21,$22,$23,$24,$25,$26,$27
7230:24 25 26
7233:27
7234:28 29 2A 439          DFB          $28,$29,$2A,$2B,$2C,$2D
7237:2B 2C 2D

723A:31 32 33 441          DFB          $31,$32,$33,$34,$35,$36,$37
723D:34 35 36
7240:37
7241:38 39 3A 442          DFB          $38,$39,$3A,$3B,$3C,$3D
7244:3B 3C 3D
```

\*\*\* SUCCESSFUL ASSEMBLY: NO ERRORS

# APPENDIX A

## DIFFERENCES BETWEEN "OLD" AND "NEW" EDASM

Apple Computer's EDASM editor/assembler has recently been overhauled and upgraded. There are now two new versions, one for DOS 3.3e, and one for ProDOS. Both are available in their respective toolkits in Apple's *Workbench* series.

The bottom line is that EDASM is now a first class, first rate macroassembler with just about all the bells and whistles anyone could ask for, including dual file editing, "library" module insertion, in-place assembly, and co-resident assembly. While the editor portion of EDASM remains as putrid as ever, you can simply use Applewriter IIe and WPL instead, doing "new way" editing as in chapter five.

Included with either EDASM is a new debugging tool called the BUGBYTER. The BUGBYTER includes a fancy upgrade of the old miniassembler, along with greatly improved single step, trace, and debug routines in a package that lets you do much more and do it much more quickly. For instance, there are single keystrokes to pick any screen mode, and you can use the game paddle to control debugging speed. You can even debug parts of your code at full speed and parts at slow speed. This is most handy for time critical routines. BUGBYTER is runnable anywhere in memory.

Very little was lost in going from "old" EDASM to "new" EDASM. With "new" EDASM, reserved labels normally include "A," "a," "X," "x," "Y," and "y," instead of just "A." You also *must* separate the op code and operand of SKP, ROL, ROR, ASL, LRS, and LST. Thus, a "SKP5" or a "ROLA" command will generate error messages under "new" EDASM. To use "old" EDASM source code with "new"

EDASM, spaces must be added between op code and operand of all these commands. Tab settings are also different in the "new" version.

Here's a list of the important changes and improvements to the editor portion of DOS 3.3e version of "new" EDASM. Note that anything you don't like about these features is easily gotten around by doing "new way" editing under Applewriter IIe instead.

Here goes:

1. The author of "old" EDASM was Randy Wigginton; the new author is John Arkley, who upgraded and improved Randy's original work.
2. The BUGBYTER is included, a tremendous improvement over the old miniassembler, single step, and trace routines.
3. System ID routines are now supplied and standardized, letting you configure your code for a II, II+, or IIe.
4. The work buffer is now 26,000 characters long, which is somewhat shorter than "old" EDASM. However, with "new way" editing under Applewriter IIe, your edit file can be 48,000 characters long.
5. The ASMDSTAMP is restricted in its form so that real time clocks can be supported.
6. The FILE command now displays the slot and drive.
7. The manuals are greatly improved and now include tutorials.
8. The command level now automatically accepts either upper or lower case.
9. Combined upper and lower case is now standard on the Apple IIe. On older Apples, new commands of SETL and SETU are available for those Apples with a shift key mod and a lower case display. Commands of [E] (shift to lower case) and [W] (shift to upper case) are available for very old Apples without lower case. The screen will not be legible in lower case on these older machines.
10. Direct DOS commands using the "." prefix are not filtered for possible damage. In particular, ".SAVE" will plow the works.
11. You still cannot insert into the middle of your source code using "old way" editing. You have to use APPEND and then COPY. With "new way" editing, you can, of course, insert anything you want any place you want any time you want.
12. There is a new VOL command that goes along with SLOT and DRIVE that will return the current disk volume in use.
13. There is a new ADD command that lets you add text beyond a certain line number. Thus ADD 16 will add new lines *beyond* old line 16, compared to INS 16 which would insert new lines *before* old line 16.
14. The INSert or ADD modes can now be stopped with either a [D] or [Q].
15. A new REPLACE mode erases and then overwrites in one step. Before you had to DElete and then INSert.
16. There now is a recovery procedure to undo the NEW command. It is hairy to use, but it does exist.
17. A command of L43-6 lists six lines starting at line 43. Any time the second number is less than the first one, it is interpreted as "how many?".
18. The [R] command will relist whatever you last asked of [L].
19. A new command of SETD lets you change the delimiter from a ":". This lets you search and replace on a colon. Space or carriage returns are not allowed as delimiters.
20. You can now edit on both a range of numbers and a search string.
21. You can edit two files at once. The command of SWAP moves the two files between the "active" and "passive" editing buffers, sort of like a [Y] split screen in Applewriter IIe. The command of KILL2 deletes the "passive" buffer, similar to a "[Y]-N" in Applewriter IIe.
22. You can pick either 40 or 80 column operation with a "COL 40" or "COL 80" command.

23. There is now a simple way to undo the END command. Just set MAXFILES 5 and Call 3075.

Here are the major improvements in the assembly portion of "new" EDASM:

1. The DOS 3.3 version of "new" EDASM will not do an assembler listing to disk. You have to use the ProDOS version if you want to capture your normally printed assembler listing as a disk text file.
2. The trailer on an assembler listing now includes the date, line count, and remaining free space.
3. An "@" following an ASM command will suppress object code generation. This is handy for "quick looks" and finding potential errors.
4. The ASMIDSTAMP is no longer essential. On "old" EDASM, a FILE NOT FOUND error message was generated.
5. You can single step the assembly process by pressing the spacebar. Repeated spacebar hits do one line at a time. Pressing [ESC] on a 40-column screen lets you see the right half of the screen, or else switches back to the left half. Any other letter key resumes assembly at full speed.
6. Two *direct* keyboard commands override any imbedded LST ON or LST OFF commands. Use [N] to stop the listing, [O] to continue it.
7. The assembler will accept the tab key, [I], or the spacebar to enter a tab. This greatly eases the "tab problem" with "new way" editing.
8. The label in the label field is now called an IDENTIFIER.
9. The "a," "X," "x," "Y," and "y" labels are now reserved, in addition to "A." You can go to a lot of trouble to defeat this reservation if you have to. Good practice would also tell you to reserve "P," "p," "S," and "s" as well.
10. Macros are now available. These are disk based and are inserted when and as needed. Parameters can be passed back and forth between source code and macro.
11. A new operand of "\*" is available that uses the present assembler program counter location. Intended use is to set aside specific positions in a page of memory. This can also be used to "pad" your way up to the next even page boundary.
12. You can now generate an absolute reference to a page zero location. To do this, put the EQU *after* the place in the source code where it first is needed. This is handy when you want to force an absolute long load, store, or whatever from an address on page zero, because of timing or code length considerations.
13. An upgraded OBJ command lets you assemble directly into the machine, without assembling to disk first. Tests are made to make sure there is no conflict with the assembly code itself. The combination of an "OBJ" command with an "ASM @" will directly assemble code into memory without generating any listing.
14. A new SW16 command will accept "Sweet 16" mnemonics. Three new commands have also been added to the original Sweet 16, which is a 16-bit pseudo interpreter. A compare, long branch, and subroutine long branch are now available. Use of Sweet 16 is usually shorter and simpler, but slower than doing your own custom 16-bit routines. One source of the new Sweet 16 code is EDASM itself. Just tear it apart using the "tearing method" of *Enhancing Your Apple II and IIE, Volume I*, (Sams 21822).
15. An undocumented X6502 command will apparently accept 65C02 mnemonics and, presumably, 65XC16 mnemonics as well. This command appeared in the preliminary documentation with a "we don't support this" disclaimer, but was dropped completely in the final manual.
16. New commands of ZDEF, ZREF, and ZXTRN are available that are

extensions of DEF. These forward-looking features require a linking loader that is not yet supported.

17. A new STR command works like ASC, only it includes a byte counter as its first character. Thus ASC gives you a text message, while STR gives you a text message preceded by the number of actual characters in the message.
18. A new DATE command reads the nine ASCII values stored at \$03B8-\$03C0 and enters them into the object code being generated. These locations usually hold the date portion of the ASMIDSTAMP.
19. A new IDNUM command reads the six ASCII values stored at \$03C3 through \$03C8 and enters them into the object code being generated. These locations usually hold the identity portion of the ASMIDSTAMP.
20. Conditional assembly has undergone a major overhaul. New commands of IFNE (not equal), IFEQ (equal), IFLT (less than), IFLE (less than or equal), IFGT (greater than), and IFGE (greater than or equal) are now available. A command of FAIL is also available for printing error messages.
21. A space must separate the op code and the operand on the SKP and LST commands.
22. Logical operators are now available, using the “↑” symbol for AND, “|” for OR, and “!” for EXOR. These operators work *only* on 16-bit arguments.
23. A new INCLUDE command stops the main assembly, assembles a source code module off disk, and then picks back up on the main assembly. This is most handy for inserting “mix and match” stock library routines.
24. Two commands of SBUFSIZ and IBUFSIZ let you adjust the size of your work areas for the original source code and the INCLUDE library module. See the manual for details. Changing buffer sizes is not normally needed.
25. A new MACLIB command tells the assembler that any “illegal” mnemonics are really the names of macro routines. Each macro routine is automatically done as if it was an INCLUDE command.
26. The “formfeed bug” has presumably been fixed, but it is still a good idea to force your own page breaks using the PAGE command.
27. A special column is available on the assembly listing to show branch destination addresses. Execution cycle times can also be optionally shown.
28. There are all sorts of new LST options. You can now separately turn off or on display of execution cycle times (C), generated object code (G), warnings (W), unassembled source code from bypassed conditional assembly (U), macro statements (E), alphabetic symbol tables (A), numeric symbol tables (V), or “six-across” symbol listings (S).
29. Standard tabbing values are different from “old” EDASM. Default tabs are now 16, 22, and 36, instead of 14, 19, 29. More than 80 columns may be needed for all the listing features and long comments. The simplest way to handle this is with 12 pitch on a daisywheel printer, or else use your own custom and “tighter” tab values. HINT: Keep your comments shorter than you did with “old” EDASM. This will help a lot.
30. New macro commands of “&0” and “&X” are available that control passing of parameters from the main source code to the macros. “&0” tells the number of parameters present in the operand field of the calling statement. “&X” keeps track of the number of times a macro is used. This allows the creation of local labels.
31. You can do co-resident assembly in a 64K Apple IIe, where the editor and assembler modules stay in the machine at the same time. An “\*” following the ASM command will get the source file out of your machine, rather than off disk. This greatly speeds up the edit-assemble-

test round trip process. On short programs in certain areas of your machine, you can do both co-resident and in-place assembly at the same time. There are restrictions: You cannot use chaining, insertion, or macros when doing this, and your source code in the machine will get overwritten.

Finally, here are the differences between the ProDOS and DOS 3.3e versions of EDASM:

1. The ProDOS buffer is 37,000 characters long.
2. The ASMIDSTAMP is severely restrictive. It must be in DD-MM-YY format for clock compatibility.
3. A blank SBTL line still gets you the date.
4. The PFX command reads the current prefix. As is typical in ProDOS, a CAT command gets you a 40 column catalog, while the CATALOG command gives you all 80 columns. The CREATE command will generate a sub-directory.
5. The TYPE command lets you edit certain other file types, rather than just text files. You can also BLOAD, BSAVE, XLOAD, and XSAVE non-text files. The SYS command changes the type of source code file.
6. The EXIT command returns you to ProDOS BASIC. Commands of PTON and PTOFF turn the printer off and on, while EXEC will do a supervisory routine.
7. Time and date are automatically inset if a clock card is present. A TIME command is supported.
8. You can no longer do co-resident assembly. Preliminary ProDOS documentation did not support macros. Editing of two files at once also may not be supported.
9. You can route an assembler listing to diskette, instead of to printer, by using a "PR#6,ZORCHFILE" command.
10. There is a PAUSE command available to temporarily hold up assembly.
11. The error message on an aborted assembly is completely useless.

I personally despise ProDOS. Why? Because it is so unconscionably bloated, so user vicious, so buggy, and so incredibly poorly written. Nonetheless, if you must make an EDASM disk-based assembler listing (for "camera ready" print quality, typesetting, insertions, etc.), you will have to use ProDOS. The procedure is to take your DOS 3.3e text file, convert it with CONVERT, assemble to disk under ProDOS, and then CONVERT it back to the sane world.

Sigh.

Both ProDOS itself and the "new" versions of EDASM have numerous bugs in them. We will pass them on to you as we find out more about them.

Several specific bugs for now: The ProDOS routine of CONVERT can sometimes destroy a DOS 3.3e diskette. Seems a sector counter doesn't get incremented properly. Long filenames will often cause assembly problems. If it does not feel too much like assembling something, the ProDOS version of EDASM will simply kick sand in your face, instead of telling you what went wrong. That "ASSEMBLY ABORTED: LINE 0" message sure is friendly and helpful.

On either "new" version of EDASM, you will get error messages on a SKP5 or a LSTOFF, or an ASLA, and other places where "old" EDASM let you skip the space between op code and operand. Unfortunately, I did this just about everywhere in this book. Correcting the printed listings would most likely cause more grief than it would solve.

So, we have instead corrected all of the source code on the companion diskette.

Just remember to be sure and separate *all* op codes and operands with a space on "new" EDASM, and you should not have too much trouble.

Let us know about any other bugs as soon as you can.

# APPENDIX B

## SOME NAMES AND NUMBERS

ANTHRO DIGITAL SYSTEMS  
Box 1385  
Pittsfield, MA 01202  
(413) 448-8278

APPLE ASSEMBLY LINE  
Box 280300  
Dallas, TX 75288  
(214) 324-2050

APPLE AVOCATION ALLIANCE  
721 Pike Street  
Cheyenne, WY 82001  
(307) 632-8581

~~A.P.P.L.E.  
304 Main South  
Renton, WA 98055  
(206) 271-4515~~

*21246 68th Ave S  
Kent WA, 98032  
(206) 872-2245*

APPLE COMPUTER  
10260 Bandley Drive  
Cupertino, CA 95014  
(408) 996-1010



AVOCET SYSTEMS  
804 South State Street  
Dover, DE 19901  
(302) 734-0151

BYTE  
70 Main Street  
Peterborough, NH 03458  
(603) 924-9281

CENTRAL POINT SOFTWARE  
Box 19730  
Portland, OR 97219  
(503) 244-5782

COMPUTER SHOPPER  
Box F  
Titusville, FL 32780  
(305) 269-3211

CREATIVE COMPUTING  
Box 789-M  
Morristown, NJ 07960  
(201) 540-0445

DENVER APPLE PI  
Box 14767  
Denver, CO 80217  
(303) 429-4436

DECISION SYSTEMS  
Box 13006  
Denton, TX 76203  
(817) 382-6353

DIABLO SYSTEMS  
24500 Industrial Blvd.  
Hayward, CA 94545  
(800) 227-2776

GENERAL INSTRUMENTS  
600 West John Street  
Hicksville, NY 11802  
(516) 733-3107

GTE ELECTRONICS  
2000 West 14th Street  
Tempe, AZ 85281  
(602) 968-4431

HARDCORE COMPUTING  
Box 44549  
Tacoma, WA 98444  
(206) 531-1684

HAYDEN SOFTWARE  
50 Essex Street  
Rochelle Park, NJ 07662  
(800) 343-1218

HOWARD W. SAMS & CO., INC.  
4300 West 62nd Street  
Indianapolis, IN 46206  
(800) 428-3696

INCIDER  
80 Pine Street  
Peterborough, NH 03458  
(603) 924-9471

INFOWORLD  
530 Lytton Avenue  
Palo Alto, CA 94301  
(415) 665-1330

INTERNATIONAL APPLE CORE  
908 George Street  
Santa Clara, CA 95050  
(408) 727-7652

DON LANCASTER  
Box 809  
Thatcher, AZ 85552  
(602) 428-4073

LAZER SYSTEMS  
925 Loma Street  
Corona, CA 91720  
(714) 735-1041

LJK ENTERPRISES  
Box 10827  
St. Louis, MO 63129  
(314) 846-6124

DAVID W. MEYER  
600 Columbus Street  
Salt Lake City, UT 84103  
(801) 359-2790

MICROCOMPUTING  
80 Pine Street  
Peterborough, NH 03458  
(603) 924-9471

MICRO INK  
34 Chelmsford Street  
Chelmsford, MA 01824  
(617) 256-3649

MICRO LOGIC CORP.  
Box 174  
Hackensack, NJ 07602  
(201) 342-6518

MICRO SCI  
17742 Irvine Blvd.  
Tustin, CA 92680  
(714) 731-9461

MICROSOFT  
10700 Northrup Way  
Bellevue, WA 98004  
(206) 828-8080

MICRO SPARC  
10 Lewis Street  
Lincoln, MA 01773  
(617) 259-9039

MITEL  
360G Leggett Drive  
Kanata, Ontario K2K 1X5  
(613) 592-5630

MOS TECHNOLOGY  
950 Rittenhouse Road  
Norristown, PA 19401  
(215) 666-7950

MOTOROLA SEMICONDUCTOR  
Box 20912  
Phoenix, AZ 85018  
(602) 244-6900

NEC ELECTRONICS  
532G Broadhollow Road  
Mellville, NY 11747  
(213) 973-2071

NCR MICROELECTRONICS  
1635 Aeroplaza Drive  
Colorado Springs, CO 80916  
(303) 596-5795

NIBBLE  
Box 325  
Lincoln, MA 01773  
(617) 259-9710

PEELINGS  
Box 188  
Las Cruces, NM 88004  
(505) 526-8364

QUALITY SOFTWARE  
6660 Reseda Blvd.  
Reseda, CA 91355  
(213) 344-6599

RAK-WARE  
41 Ralph Road  
West Orange, NJ 07052  
(201) 325-1885

ROCKWELL INTERNATIONAL  
3310 Miraloma Avenue  
Anaheim, CA 92803  
(800) 854-8099

SAN FRANCISCO APPLE CORE  
1515 Sloat Blvd.  
San Francisco, CA 94132  
(415) 556-2324

S-C SOFTWARE  
Box 280300  
Dallas, TX 75228  
(214) 324-2050

SIERRA ON-LINE  
36575 Mudge Road  
Coarsegold, CA 93614  
(209) 683-6858

SOFTALK  
11160 McCormick Street  
North Hollywood, CA 91603  
(213) 980-5074

SOUTHWESTERN DATA SYSTEMS  
10761 Woodside Avenue  
Santee, CA 92071  
(619) 562-3221

STELLATION TWO  
Box 2342  
Santa Barbara, CA 93120  
(805) 966-1140

SYNERGETICS  
Box 1300  
Thatcher, AZ 85552  
(602) 428-4073

SYNERTEK  
Box 552  
Santa Clara, CA 95052  
(408) 988-5600

TEXAS INSTRUMENTS

Box 401560  
Dallas, TX 75240  
(214) 995-6611

THUNDER SOFTWARE

Box 31501  
Houston, TX 77231  
(713) 728-5501

WASHINGTON APPLE PI

Box 34511  
Bethesda, MD 20817  
(202) 332-9012

WESTERN DESIGN CENTER

2166 East Brown Road  
Mesa, AZ 85203  
(602) 962-4545

# APPENDIX C

## **LABEL LISTS TO COPY**

**LABEL LIST FOR**

DONE BY  ASSEMBLER

DATE  -- -- SYSTEM

VERSION

LABEL	EQU	LINE	DFB	VALUE	USE

NOTES \_\_\_\_\_  
\_\_\_\_\_  
\_\_\_\_\_

PAGE  OF

# LABEL LIST FOR

DONE BY  ASSEMBLER

DATE  -  -  SYSTEM

VERSION

LABEL	EQU	LINE	DFB	VALUE	USE

NOTES \_\_\_\_\_  
\_\_\_\_\_  
\_\_\_\_\_

PAGE  OF



# Index

## A

- Absolute
  - addressing, 75
  - pitch, 303
- Accumulator addressing, 73
- Accuracy, pitch, 302-304
- Active line, 167
- ADD editing command, old way, 146
- Address mode, 72-81
- Addressing
  - absolute, 75
  - accumulator, 73
  - immediate, 73-74
  - implied, 72-73
  - indexed, 76-80
  - indexed indirect, 79-81
  - indirect, 77-81
  - indirect indexed, 77-81
  - page zero, 74-75
  - relative, 75
- Anthologies, assembler, 52
- APPEND, DOS editing command,
  - old way, 142-143
- Apple clock cycle, 268-269
- Arithmetic, operand, 81-82
- ASC pseudo-op, 89-90
- ASM assembler commands, 179-180
- Assemblers, 25-56
  - anthologies, 52
  - BUGBYTER, 30
  - club newsletters, 51-52
  - commands, 178-181
    - ASM, 179-180
  - comments, 29
  - cross, 34-35
  - defined, 39
  - disk-based, 33-34
  - EDASM, 42-44
  - full, 30, 35-36
  - how work, 35-41
  - in-place, 33-34
  - label, 28
    - global, 31-32
    - local, 31-32
  - language, 27
  - listing, 96-97
  - machine programming books, 49-50
  - macro-, 30, 31, 35
  - mini-, 28-30, 35
  - mnemonic, 27-28
  - modular, 34

Assemblers—cont  
  object code, 36-38  
  relocatable code, 32-33  
  reprints, 52  
  resources, 44-46  
  software, 50  
  source code, 36-41  
  tools, 44-49  
  virtual memory, 32  
Assembling source code, 177-200  
Assembly  
  books, 49-50  
  language, 9-22, 27  
  listings, 181-185  
  magazines, 51-52  
  rules, EDASM, 178

**B**

Bad  
  equate, 189-190  
  expression, 188-189  
  op code, 188  
BASIC, 11-15, 16  
Big lumps, source code, 110-113  
Books  
  assembly, 49-50  
  machine programming, 49-50  
Bottom line comments, 118  
BUGBYTER, 30

**C**

Calculated routine method, 291-295  
CATALOG, DOS editing command,  
  old way, 143-144  
[C] assembler command, 180-181  
CHANGE editing command, old way,  
  155  
CHN pseudo-ops, 85-86  
Clock cycle, Apple, 268-271  
Club newsletters, assembler, 51-52  
Code  
  object, 36-38  
  op, field, 63-64, 67  
  relocatable, 32-33  
  source, 36-41  
    details, 57-92  
  fields, 62-72  
  file line numbers, 59-61  
Commands  
  assembler, 178-181  
  editing, old way, 139-161  
Comments, 29  
  bottom line, 118  
  line, 167-168  
  field, 68-70

Conditional pseudo-ops, 90  
Constants, 109-110  
  EQU, 109-110  
COPY editing command, old way, 149  
Creating files, 238-240  
Cross assembler, 34-35  
Crumbs, source code, 110-114, 116  
Cycle burner uppers, 269-270

**D**

Debugging, 192-198  
  stage-one, 195  
  stage-two, 197-198  
  weirdness checks, 197  
DELETE editing command, old way,  
  148-149  
DFB  
  hook, 107-108  
  pseudo-ops, 87-89  
Disassemblers, 52-54  
Disk-based assembler, 33-34  
DOS editing commands, old way,  
  140-144  
  APPEND, 142-143  
  CATALOG, 143-144  
  LOAD, 140-141  
  SAVE, 141-142  
  SLOT DRIVE, 143  
Dot-matrix printers, 45-46  
Duplicate symbol, 189  
Duration multiplier, 306-308

**E**

EDASM, 42-44  
  assembly rules, 178  
  macroassembler, 20-21  
  Old, new, 381-386  
Edit editing commands, old way,  
  152-158  
  EDIT, 152-154  
Editing  
  “new way,”  
    advantages, 164  
    limitations, 165  
    source code, 163-175  
  old way, commands, 139-161  
  ADD, 146  
  CHANGE, 155  
  COPY, 149  
  DELETE, 148-149  
  DOS, 140-144  
  edit, 152-158  
  END, 147  
  FIND, 154-155  
  (HELP), 146

## Editing—cont

*old way, commands*

INSERT, 146  
 LENGTH, 150  
 LIST, 148  
 NEW, 146  
 QUIT, 146-147

hint, *old way*, 156source code, *old way*, 123-161

Editor, 39-41

Empty shell, 211-228

END editing command, *old way*, 147

Enhancements, 105

Entry editing commands, *old way*,  
146-152

## EQU

constants, 109-110

hooks, 107-109

pseudo-ops, 85-86

## Error

handling, 191-192

messages, 119-121, 185-191

fatal, 185, 186-188

handling, 191-192

nonfatal, 185-186, 188-191

## F

## Fields

comment, 68-70

label, 63, 64-67

op code, 67

operand, 67-68, 70-72

source code, 62-72

## File

based printer, 229-250

creating, 238-240

long method, 233-240

message, 233-234, 238-239

pointer, 233-234, 239-240

pseudo-ops, 87-90

source code, 37-41

formats, 58-64

line numbers, 59-61

structure, 166-169

working, 114-118

FIND editing command, *old way*,  
154-155

Formats, file, source code, 58-64

Full assembler, 30, 35-36

## G

Global label, 31-32

Gotchas, 104-105

## H

Handling errors, 191-192

(HELP), editing command, *old way*, 146Hint, editing, *old way*, 156

Hooks, 106-109

DFB, 107-108

EQU, 107-109

## I

ID stamp, 137-138

Illegal label, 189

Imbedded string printer, 251-266

Immediate addressing, 73-74

Implied addressing, 72-73

Indexed addressing, 76-80

indirect, 79-81

Indirect addressing, 77-81

indexed, 77-81

In-place assembler, 33-34

INSERT editing command, *old way*, 146Integer pseudo-random generator,  
348-350

## L

Label, 28, 64-67

field, 63, 64-67

global, 31-32

lists, 393-398

*old way*, 156-159

local, 31-32

references, 118-119

## Language

assembly, 9-22, 27

BASIC, 11-15, 16

machine, 9-22, 25-26

## LENGTH

editing command, *old way*, 150

program style, 127-129

## Line

active, 167

comment, 167-168

numbers, 169-173

file, source code, 59-61

LIST editing command, *old way*, 148

Listing, assembler, 96-97

Little lumps, source code, 110-114

LOAD, DOS editing command, *old way*,  
140-141

Local label, 31-32

Long file method, 233-240

Lookup, table, 125

LST OFF pseudo-op, 84

ST ON pseudo-op, 84

**M**

Machine  
 language, 9-22, 25-26  
 programming books, 49-50  
 Macro-, 31  
 assembler, 30, 35  
 EDASM, 20-21  
 Magazines, assembly, 51-52  
 Memory, virtual, 32  
 Messages  
 error, 119-121, 185-191  
 file, 233-234, 238-239  
 Miniassemblers, 28-30, 35  
 Mnemonic, 27-28  
 Mode, address, 72-81  
 Modular assembler, 34  
 Modules, ripoff, 205-380  
 Modulo, 346  
 Monitor time delay, 267-286  
 Musical songs, 301-320

**N**

New  
 EDASM, 381-386  
 editing command, old way, 146  
 -Way editing  
 advantages, 164  
 limitations, 165  
 Newsletters, club, assembler, 51-52  
 N initializer, 352-353  
 No such label, 189  
 Numbers,  
 file line, source code, 59-61  
 line, 169-173

**O**

Object code, 36-38  
 assembling source code, 177-200  
 files, 37-41  
 Obnoxious sounds, 287-300  
 Off loading, 125-126  
 Old  
 EDASM, 381-386  
 -way source code writing, 135-140  
 Op code field, 63-64, 67  
 Operand  
 arithmetic, 81-82  
 field, 67-68, 70-72  
 summary, 80  
 Option picker, 321-344  
 ORG pseudo-op, 84-85  
 Overflow, 190

**P**

PAGE  
 pseudo-ops, 83  
 zero addressing, 74-75  
 Pitch  
 absolute, 303  
 accuracy, 302-304  
 duration, separating, 304-306  
 relative, 303  
 Pointer file, 233-234, 239-240  
 Pretty printer pseudo-ops, 83  
 Print editing commands, old way,  
 144-146  
 PR#0,1, 145-146  
 Printers, dot matrix, 45-46  
 Processors, word, 163-167, 168-173  
 Program style, 124, 133  
 length, 127-129  
 speed, 124-127  
 PR#0, 1, print editing commands, old  
 way, 144-146  
 Pseudo-ops, 82-87  
 conditional, 90  
 file, 87-90  
 ASC, 89-90  
 DFB, 87-89  
 LST OFF, 84  
 LST ON, 84  
 PAGE 83  
 pretty printers, 83  
 SBTL, 84  
 SKP, 83  
 structure, 84-87  
 CHN, 85-86  
 EQU, 85-86  
 ORG, 84-85  
 Pseudo-random number, 345, 347-350  
 PSR generator, 352-353

**Q**

QUIT editing command, old way,  
 146-147

**R**

Random  
 comments, 105-106  
 numbers, 345-362  
 Randomizing, 364  
 replacement, 364  
 References, label, 118-119  
 Relative  
 addressing, 75  
 pitch, 303  
 Relocatable code, 32-33

Relocatability, code, 130-131  
 Reprints, assemblers, 52  
 Reseeder, 352-353  
 Resources, assembler, 44-46  
 Ripoff modules, 205-380  
   summary, 208-209  
 RND; see random numbers.  
 Routine method, calculated, 291-295

## S

SAVE, DOS editing command, old way,  
   141-142  
 SBTL pseudo-ops, 84  
 Self-modifying code, 132  
 Separating pitch, duration, 304-306  
 Shuffle, 363-380  
 SKP pseudo-ops, 83  
 SLOTDRIVE, DOS editing command, old  
   way, 143  
 Software, assembly programming, 50  
 Source code, 36-41  
   address mode, 72-81  
   addressing  
     absolute, 75  
     accumulator, 73  
     immediate, 73-74  
     implied, 72-73  
     indexed, 76-80  
     indexed indirect, 79-81  
     indirect, 77-81  
     indirect indexed, 77-81  
     page zero, 74-75  
     relative, 75  
     ssembling, 177-200  
   \_details, 57-92  
   fields, 62-72  
     comment, 68-70  
     op code, 67  
     operand, 67-68, 70-72  
   files, 37-41  
     formats, 58-64  
     line numbers, 59-61  
     structure, 166-169  
   labels, field, 63, 64-67  
   new way, editing, 163-175  
     line numbers, 169-173  
   new way, writing, 163-175  
   old way editing, 123-161  
     commands, 139-161  
     DOS commands, 140-144  
     edit, 152-158  
     entry commands, 146-152  
     print commands, 144-146  
   old way writing, 123-161  
     ID stamp, 137-138  
     style, 124-133  
     unstyle, 133-135

Source code—cont  
   op code fields, 63-64  
   operand  
     arithmetic, 81-82  
     summary, 80  
   pseudo-ops, 82-87  
   relocatability, 130-131  
   structure, 93-122  
     big lumps, 110-113  
     body, 97-98  
     bottom line comments, 118  
     constants, 109-110  
     crumbs, 110-114, 116  
     enhancements, 105  
     error messages, 119-121  
     gotchas, 104-105  
     hooks, 106-109  
     little lumps, 110-114  
     prolog, 97-98  
     random comments, 105-106  
     self-modifying, 132  
     startstuff, 98-101  
     stashes, 115-116  
     title block, 101-103  
     working files, 114-118  
 Space assembler command, 181  
 Speed, program style, 124-127  
 Stack rules, subroutine, 6502, 254-255  
 Stage-one debugging, 195  
 Stage-two debugging, 197-198  
 Startstuff, 98-101  
 Stashes, 115-116  
 Structure  
   file, source code, 166-169  
   pseudo-ops, 84-87  
   source code, 93-122  
 Style, program, 124-133  
 Subroutine stack rules, 6502, 254-255  
 Sweet 16, 198-200

## T

Tab, 173-175  
 Table lookup, 125  
 Threshold, viability, 195  
 Title block, 101-103  
 Tools, assembler, 44-49

## U

Unstyle, 133-135

## V

Viability threshold, 195  
 Virtual memory, 32

**W**

- Weirdness checks, debugging, 197
- Word processors, 163-167, 168-173
- Working files, 114-118
- Writing source code, new way, 163-175
  - old way, 123-161

**Book begins as Part One at**  
**<http://www.tinaja.com/ebooks/aacb1.pdf>**

**SYNERGETICS SP PRESS**  
**3860 West First Street, Thatcher, AZ 85552 USA**  
**(928) 428-4073 <http://www.tinaja.com>**

**ISBN: 978-1-882193-17-2**

# **Assembly Cookbook for the Apple™ II/IIe**

## **( part two )**

**Your complete guide to using assembly language for writing your own top notch personal or commercial programs for the Apple II and IIe.**

- **Tells you what an assembler is, discusses the popular assemblers available today, and details the essential tools for assembly language programming.**
- **Covers source code details such as lines, fields, labels, op codes, operands, structure, and comments-just what these are and how they are used.**
- **Shows you the "new way" to do your source code entry and editing and to instantly upgrade your editor/assembler into a super-powerful one.**
- **Shows you how to actually assemble source code into working object code. Checks into error messages and debugging techniques.**
- **Includes nine ready to go, open ripoff modules that show you examples of some of the really essential stuff involved in Apple programming. These modules will run on most any brand or version of Apple or Apple clone, and they can be easily adapted to your own uses.**

**This cookbook is for those who want to build up their assembly programming skills to a more challenging level and to learn to write profitable and truly great Apple II or IIe machine language programs.**

**SYNERGETICS SP PRESS**

**3860 West First Street, Thatcher, AZ 85552 USA  
(928) 428-4073 <http://www.tinaja.com>**

**ISBN: 978-1-882193-17-2**